



Camtasia Help

Version 2024 | January 2025

All rights reserved

This manual, as well as the software described in it, is furnished under license and may be used or copied only in accordance with the terms of such license. The content of this manual is furnished for informational use only, is subject to change without notice and should not be construed as a commitment by TechSmith Corporation. TechSmith Corporation assumes no responsibility or liability for any errors or inaccuracies that may appear in this manual.

Trademarks


All-In-One Capture, Audiate, Camtasia, Camtasia Studio, Coach's Eye, C Icon, EnSharpen, Enterprise Wide, Jing, Knowmia, Morae, Rich Recording Technology (RRT), Screencast, Screencast.com, Screentelligence, SmartFocus, Snagit, S Icon, TechSmith, TechSmith and T Design Logo, TechSmith Academy, TechSmith Assets, TechSmith Audiate, TechSmith Camtasia, TechSmith Capture, TechSmith Fuse, TechSmith Knowmia, TechSmith Motion, TechSmith Relay, TechSmith Screencast, TechSmith Snagit, TechSmith Smart Player, TechSmith Video Review, TSCC, and Video Review are either registered marks or marks of TechSmith Corporation in the U.S. and/or other countries. This list is not a comprehensive list of all TechSmith Corporation marks. The absence of a name/mark or logo in this notice does not constitute a waiver of any intellectual property rights that TechSmith Corporation has established in any of its product, feature or service names/marks or logos. All other marks are the property of their respective owners.

What's New in Camtasia 2024

Learn about new features and improvements in Camtasia 2024.

Discover what's new in [Camtasia 2024](https://www.techsmith.com/camtasia) (<https://www.techsmith.com/camtasia>).

Captions




Dynamic Captions

Add dynamic captions to automatically transcribe audio on the timeline into customizable onscreen caption text. Perfect for social media videos!

In version 2024.1 you can adjust the timing to ensure a perfect sync between your voice and transcription.

See [Add Dynamic Captions](https://www.techsmith.com/learn/tutorials/camtasia/dynamic-captions/) (<https://www.techsmith.com/learn/tutorials/camtasia/dynamic-captions/>).




Speech-to-Text Closed Captions

On Windows, easily add closed captions with new AI speech-to-text capabilities.

See [Add Closed Captions to a Video](https://www.techsmith.com/learn/tutorials/camtasia/add-closed-captions/) (<https://www.techsmith.com/learn/tutorials/camtasia/add-closed-captions/>).

Camtasia Rev Workflow Enhancements

Whether you are starting a new screen recording or enhancing existing media, use the Rev workflow for quick sizing, layout, background, effect, and filter choices to accelerate your video creation.



See [Apply Quick Layouts & Effects with Camtasia Rev](https://www.techsmith.com/learn/tutorials/camtasia/record-edit-share/import-to-camtasia-rev/) (<https://www.techsmith.com/learn/tutorials/camtasia/record-edit-share/import-to-camtasia-rev/>).

Camtasia Assets Integration

Assets are now easier than ever to access and add to your projects! Browse over 100 million professional, royalty-free video assets directly in Camtasia. Add polish to your video with photos, videos, audio, and customizable digital content, without ever leaving the editor!

Search for and apply assets right in the Camtasia editor. Plus, we've enhanced the search for more rich results. See [Enhance Your Video with Camtasia Assets](https://www.techsmith.com/learn/tutorials/camtasia/camtasia-assets/) (<https://www.techsmith.com/learn/tutorials/camtasia/camtasia-assets/>).



Progress Bars & Timers

Choose from a variety of ready-made progress bars and timers for a variety of uses. In Camtasia Editor, select **Media tab > Camtasia Assets subtab > Audio Visualizers category**.




New Audio Visualizers

We've added even more ways to add visual enhancement to your audio.

Visualize your voice narration, music clips, sound effects, or any audio to transform static video into dynamic onscreen audio animations.

See [4 Ways to Visualize Audio](https://www.techsmith.com/learn/?post_type=tutorial&p=243902) (https://www.techsmith.com/learn/?post_type=tutorial&p=243902).




New Dynamic Backgrounds

Choose from 57 new Dynamic Backgrounds, including Expansion, Northern Lights, Shimmering Bars, Blueprint, and more!

See [Add a Dynamic Background](https://www.techsmith.com/learn/?post_type=tutorial&p=238639) (https://www.techsmith.com/learn/?post_type=tutorial&p=238639).

New Cursor Effects



Cursor Glow

Give your cursor a glow effect to stand out on the screen and grab viewers' attention.

See [Edit the Cursor with Effects](https://www.techsmith.com/learn/tutorials/camtasia/cursor-effects/) (<https://www.techsmith.com/learn/tutorials/camtasia/cursor-effects/>).



Editable Cursor Clicks

Easily add or remove cursor clicks from your video.

Cursor Click Scaling

Emphasize mouse clicks in your screen recording with a cool scale-down effect.

See [Edit the Cursor with Effects](https://www.techsmith.com/learn/tutorials/camtasia/cursor-effects/) (<https://www.techsmith.com/learn/tutorials/camtasia/cursor-effects/>).

New Visual Effects & Animations



Tiling

Apply a tiling effect to repeat media horizontally and vertically across the screen. Great for branded backgrounds!

See [Visual Effects Overview](https://www.techsmith.com/learn/tutorials/camtasia/visual-effects/) (<https://www.techsmith.com/learn/tutorials/camtasia/visual-effects/>).



Text Stroke

Easily apply an outline effect to text. Great for adding a bit of flair or when you want extra emphasis.

New Behaviors

Tremble and Wiggle effects now available in Behaviors.

See [Animate Text & Images with Behaviors \(https://www.techsmith.com/learn/tutorials/camtasia/animation-behaviors/\)](https://www.techsmith.com/learn/tutorials/camtasia/animation-behaviors/).

New Transitions

19 brand new transitions to add more flair and creativity to your video.

See [Add a Transition \(https://www.techsmith.com/learn/tutorials/camtasia/video-transitions/\)](https://www.techsmith.com/learn/tutorials/camtasia/video-transitions/).

New Recording Engine

Capture your screen, camera, and audio in even higher fidelity.

Editing Efficiency

Reorder Tools in Camtasia Editor

Click and drag tool tabs to rearrange their order. See [Customize Camtasia \(Favorites, Presets, & More\) \(https://www.techsmith.com/learn/tutorials/camtasia/customize-camtasia/\)](https://www.techsmith.com/learn/tutorials/camtasia/customize-camtasia/).

Assign Color Labels to Media on the Timeline

Organize your timeline visually by assigning colors to clips. Easily identify and differentiate media, streamlining your editing process and saving time. See [Customize Camtasia \(https://www.techsmith.com/learn/tutorials/camtasia/customize-camtasia/\)](https://www.techsmith.com/learn/tutorials/camtasia/customize-camtasia/).



Editor Shortcuts

Make editing even faster with assignable shortcuts. See [Customize Shortcuts](https://www.techsmith.com/learn/tutorials/camtasia/customize-camtasia-shortcuts/) (<https://www.techsmith.com/learn/tutorials/camtasia/customize-camtasia-shortcuts/>).

JKL Enhancements

Save on editing time with the JKL keyboard shortcuts to speed up video play back or scrub to a precise frame.

Build Your First Video

Learn how to set up a recording, complete basic video edits, and share your video.

1. Record Your Screen & Camera


Camtasia Recorder captures your screen, camera, and audio.

▼ Set Up Your Recording




1. Select the recording area:

- Click the toggle to turn screen recording on or off.




- Click the dropdown and select a recording area option.




2. Camtasia highlights the selected recording area on the screen. To edit the recording area:


- Drag the handles to adjust the selection.



- To enter a specific size, type the dimensions in pixels into the **Width** and **Height** fields.




- To move the selected area on the screen, click the center handle (Windows) or within the selected area (Mac) and drag to the desired location.




- If your computer is connected to multiple displays, you can drag the selected area from one screen to another.

3. To record video from a built-in or connected camera device, click the toggle to turn camera recording on or off and select a camera device from the dropdown. See [Record & Edit Camera Video \(Picture-in-Picture\)](https://www.techsmith.com/blog/?post_type=tutorial&p=182351) (https://www.techsmith.com/blog/?post_type=tutorial&p=182351).




4. To record audio from your computer's built-in microphone or from a connected USB microphone:
 - Click the toggle to turn microphone recording on or off and select an audio device from the dropdown.



- Drag the slider to increase or decrease the audio level.

5. Turn system audio on or off. System audio captures the sound from your computer such as application alerts or audio playing from your computer speakers.



6. Start recording:

- **Windows:** Click the **Record** button or press **F9** on the keyboard.
- **Mac:** Click the **Start Recording** button or press **Command +Shift+2** on the keyboard.

7. Stop recording:

- **Windows:**

- Click the **Stop** button on the recording toolbar.
- Or, press **F10** on the keyboard.
- Or, click the **Camtasia Recorder icon** in the taskbar and then click the **Stop** button.



- **Mac:**

- Click **Stop Recording** on the recording toolbar.
- Or, press **Command+Option+2** on the keyboard.
- Or, click the **Camtasia icon** in the menu bar and select **Stop Recording**.



▼ Recording Tips

- **Hide desktop icons (Mac only):** Before recording your desktop, hide app, folder, and file icons. In the menu bar, select **Camtasia icon > Hide Desktop Icons**.
- **Run a sample recording to test the audio:**
 - **No Microphone Audio:** Select an audio device in the dropdown or enable the Microphone option in the recorder.
 - **No System Audio:** Enable the System Audio option in the recorder.
 - **Low Microphone Audio:** Drag the audio slider to increase the audio level and make sure the connected audio device is positioned near the speaker.
- **Customize shortcuts:** Speed up your workflow with recorder shortcuts. See [Customize Shortcuts \(https://www.techsmith.com/blog/?post_type=tutorial&p=182359\)](https://www.techsmith.com/blog/?post_type=tutorial&p=182359).
- **Record with a connected USB microphone:** For greater reliability, use a connected USB rather than Bluetooth microphone.
- **Set maximum frame rate (Windows only):** To ensure quality video recording, set the maximum capture frame rate. In Camtasia Recorder, select **Tools menu > Preferences > Inputs tab > Maximum capture frame rate**. See [Crisp & Clear Screen Recordings \(https://www.techsmith.com/blog/?post_type=tutorial&p=182307\)](https://www.techsmith.com/blog/?post_type=tutorial&p=182307) and [Camtasia Target Capture Frame Rate \(https://support.techsmith.com/hc/en-us/articles/360040788091\)](https://support.techsmith.com/hc/en-us/articles/360040788091).
- **Select a recording encoder (Windows only):** Consider whether the default TSC2 encoder or H264 encoder is better for your situation. In Camtasia Recorder, select **Tools menu > Preferences > Inputs tab > Recording encoder**. See [When to Use TSC2 vs H264 in Camtasia for Screen Recording \(https://support.techsmith.com/hc/en-us/articles/360042592752-When-to-Use-TSC2-vs-H264-in-Camtasia-for-Screen-Recording\)](https://support.techsmith.com/hc/en-us/articles/360042592752-When-to-Use-TSC2-vs-H264-in-Camtasia-for-Screen-Recording).

2. Accelerate Video Creation with Camtasia Rev

After recording, Camtasia Rev opens. Rev makes it easy for creators to deliver on-trend and compelling video content. Implement your own personal style with just a few clicks.

Size

Set the video size based on where you want to host or share the video. Rev provides size options to target standard video sizes for all your channels.

Layout

Choose from a series of layouts based on the content in your recording.

Background

Choose from a variety of colors, patterns, and animations for the background to make your content more visually engaging.

Effects

Apply multiple effects to the cursor, camera, and screen recording to draw attention or set the tone.

Filters

Apply visual filters to enhance the appearance of camera video.

Note: You can turn off some of the automatic selections in Camtasia Rev, such as backgrounds. Click to deselect the option on the **Background**, **Effects**, or **Filters** tabs.

3. Export Your Video or Edit in Camtasia


Export your video directly from Camtasia Rev. Or click **Edit in Camtasia** for further editing and enhancements, such as the following:

- Try some of our [recommended basic edits \(https://www.techsmith.com/learn/tutorials/camtasia/basic-video-edits/\)](https://www.techsmith.com/learn/tutorials/camtasia/basic-video-edits/) to make after recording.
- Add a title or one of the 100 million customizable and creative assets available in Camtasia. From right within Camtasia Editor, access intros, templates, graphics, music tracks, animations, footage, and more! See [Enhance Your Video with Camtasia Assets \(https://www.techsmith.com/learn/tutorials/camtasia/camtasia-assets/\)](https://www.techsmith.com/learn/tutorials/camtasia/camtasia-assets/).
- Use text-based editing to edit and improve your audio and generate captions in Camtasia Audiate. See [Speed Up Editing with Camtasia Audiate \(https://www.techsmith.com/learn/tutorials/camtasia/camtasia-audio-sync/\)](https://www.techsmith.com/learn/tutorials/camtasia/camtasia-audio-sync/).
- Import another recording or footage from others into Camtasia Rev for a consistent look and layout in your video. See [Apply Quick Layouts & Effects with Camtasia Rev \(https://www.techsmith.com/learn/tutorials/camtasia/import-to-camtasia-rev/\)](https://www.techsmith.com/learn/tutorials/camtasia/import-to-camtasia-rev/).

Assemble Your Video

Learn how to add media and other assets to assemble the content for your video.

The **Media** tab helps you organize and assemble content for your video. You can import media from your computer, manage media in the project, search our royalty-free assets, or use any custom assets saved to your library.



To add content to your video, continue with the following:

1	Add Media to Your Project (Media Bin)
2	Enhance Your Video with Camtasia Assets
3	Use Media from Your Personal Library

Add Media to Your Project

The Media Bin contains any media you record or add to your current video project. Select any of the following options to add content into the Media Bin to use in your video:

▼ Record the Screen

See [Build Your First Video \(https://www.techsmith.com/learn/tutorials/camtasia/record-edit-share/\)](https://www.techsmith.com/learn/tutorials/camtasia/record-edit-share/).

▼ Import Media from Your Computer

1. Click the **Media** tab.
2. Click **+** > **Import Media** or double-click in the Media Bin.
3. Click to select the media to import. **Control+click** (Windows) or **Command+click** (Mac) to select multiple files.
4. Click **Open** (Windows) or **Import** (Mac).

The imported media appears in the Media Bin.

▼ Record a PowerPoint Presentation

See [Record a PowerPoint Presentation \(https://www.techsmith.com/learn/tutorials/camtasia/record-a-powerpoint-presentation/\)](https://www.techsmith.com/learn/tutorials/camtasia/record-a-powerpoint-presentation/).

▼ Import PowerPoint Slides

See [Import PowerPoint Slides \(https://www.techsmith.com/learn/tutorials/camtasia/import-powerpoint-slides/\)](https://www.techsmith.com/learn/tutorials/camtasia/import-powerpoint-slides/).

▼ Import Media into Camtasia Rev to Apply Quick Layouts & Effects

Import a recording or footage from others into Camtasia Rev to apply a consistent look and layout in your video. See [Apply Quick Layouts & Effects with Camtasia Rev \(https://www.techsmith.com/learn/tutorials/camtasia/import-to-camtasia-rev/\)](https://www.techsmith.com/learn/tutorials/camtasia/import-to-camtasia-rev/).

▼ Record an iOS Device

See [Record an iOS Demo or Tutorial \(https://www.techsmith.com/learn/tutorials/camtasia/recording-your-ios-device/\)](https://www.techsmith.com/learn/tutorials/camtasia/recording-your-ios-device/).

▼ Import Media from a Mobile Device

Send images or videos to Camtasia from your mobile device.

1. Select **File > Connect to Mobile Device**.
2. Follow the onscreen instructions in the Connect Mobile Device dialog.

The imported media appears in the Media Bin. See [Record an iOS Demo or Tutorial](https://www.techsmith.com/learn/tutorials/camtasia/recording-your-ios-device/)

▼ Import Media from Google Drive

1. Click the **Media** tab.
2. Click  icon > **Import From Google Drive**.
3. Enter your Google email and password.
4. Click to select the media to import. **Control+click** (Windows) or **Command+click** (Mac) to select multiple files.
5. Click **Import**.

The imported media appears in the Media Bin.

▼ Record Voice Narration

See [Record Voice Narration \(https://www.techsmith.com/learn/tutorials/camtasia/record-voice-narration/\)](https://www.techsmith.com/learn/tutorials/camtasia/record-voice-narration/) (Camtasia Editor) or [Record a Voice-Over \(https://www.techsmith.com/learn/tutorials/audiate/record-a-voice-over/\)](https://www.techsmith.com/learn/tutorials/audiate/record-a-voice-over/) (Camtasia Audiate).


To include the media in your video, select **Media tab > Media Bin subtab**. Drag the media onto the desired location on the timeline or canvas.

To learn more about managing your project media in the Media Bin, see [Import & Manage Project Media \(Media Bin\) \(https://www.techsmith.com/learn/tutorials/camtasia/import-manage-media/\)](https://www.techsmith.com/learn/tutorials/camtasia/import-manage-media/).

Add Professionally-Designed Titles, Footage, Audio, & Other Assets

Assets are now easier than ever to access and add to your projects. You can browse over 100 million professional, royalty-free video assets directly in Camtasia. Add polish to your video with photos, videos, audio, and customizable digital content, without ever leaving the editor.

If you are starting with a blank Camtasia project, browse our premade assets for inspiration, such as adding a title to introduce your video or add context to a recording.




Select **Media tab > Camtasia Assets subtab** to browse or search our free and premium online assets. To add an asset to your video, drag the asset from the **Camtasia Assets** subtab onto the desired location on the timeline or canvas.

To learn more about Camtasia assets and how to use the assets in your videos, see [Enhance Your Video with Camtasia Assets \(https://www.techsmith.com/learn/tutorials/camtasia/camtasia-assets/\)](https://www.techsmith.com/learn/tutorials/camtasia/camtasia-assets/).

Note: To access online assets in Camtasia version 2023.2.0 or earlier, click the **Download button > Download more assets**. See [Find Camtasia Assets on the Website \(https://www.techsmith.com/learn/tutorials/camtasia/install-assets/\)](https://www.techsmith.com/learn/tutorials/camtasia/install-assets/) tutorial.

Use Media from Your Personal Library

The library stores any custom assets or media you want to reuse across multiple Camtasia projects. Save intros, animated backgrounds, icons, titles, music, groups, annotations, and more to your library to use consistent elements across your videos.



Select **Media tab** > **Library subtab** to browse your saved assets or media. To add a library asset to your video, drag the asset from the **Library** subtab onto the desired location on the timeline or canvas.

To learn how to save and organize assets in your library to reuse across projects, see [Reuse Assets Across Projects \(Library\)](https://www.techsmith.com/learn/tutorials/camtasia/library/) (<https://www.techsmith.com/learn/tutorials/camtasia/library/>).

Get tips on how to position media or assets.

See [Position Media on the Canvas](https://www.techsmith.com/learn/tutorials/camtasia/working-with-the-canvas/) (<https://www.techsmith.com/learn/tutorials/camtasia/working-with-the-canvas/>) or [Explore the Timeline](https://www.techsmith.com/learn/?post_type=tutorial&p=182300) (https://www.techsmith.com/learn/?post_type=tutorial&p=182300) to get recommendations on how to position media on the canvas or timeline.

Basic Edits After Recording

Learn how to apply our recommended edits after completing your recording and enhancements in Camtasia Rev.

Camtasia Editor Overview

In Camtasia Rev, click the **Edit in Camtasia** button to further customize and edit your recording in Camtasia Editor.



Note: You can turn off some of the automatic selections in Camtasia Rev, such as backgrounds. Click to deselect the option on the **Background**, **Effects**, or **Filters** tabs.

Camtasia adds your recording to the timeline and Media Bin.

- The [Media Bin](https://www.techsmith.com/learn/?post_type=tutorial&p=182296) stores all the media in your current project and maintains a copy of the original, unedited media.
- The [timeline](https://www.techsmith.com/learn/?post_type=tutorial&p=182300) is where you arrange and edit media in your video.



1. **Screen Recording**
2. **Camera Recording**
3. **Background**
4. **Effects Tray:** Click to expand the effects tray to view the effects and filters applied in Camtasia Rev.

Basic Edits

Try these quick edits after recording to remove mistakes or to customize your video.

Trim


Remove any extra content at the beginning or end of a recording.

1. Click to select the media on the timeline.
2. Drag the end of the clip in.
3. To restore content that was trimmed too far, drag the end of the clip back out.
Trimming does not affect the original recording in the media bin.

Cut Out Mistakes

Remove mistakes or unwanted sections in your content.

1. Drag the red or green handle on the playhead to select the area to remove.
2. Click the **Cut** icon to remove the section.



A dashed line appears where the clips were stitched together after the cut.

Tip: Undo a selection.

Double-click the playhead to bring the red and green handles back together.

Position Screen or Camera Recording

You can further customize your content in the Rev layout you selected. For example, move your webcam to display on the left instead of the right in your video.

1. In the Canvas toolbar, select **Edit** mode.



2. To move the screen or camera recording, click and drag the content to the desired location on the canvas.
3. To resize the screen or camera recording, click to select the content on the canvas. Drag a corner handle in or out on the canvas or drag the **Scale** slider in the properties.

To learn more about editing the camera recording, see [Record & Edit Camera Video \(Picture-in-Picture\)](https://www.techsmith.com/learn/?post_type=tutorial&p=182351) (https://www.techsmith.com/learn/?post_type=tutorial&p=182351).

Frame Content

Camtasia Rev automatically positions your content to fit within the selected layout.

To edit the content in focus in the frame:

1. In the Canvas toolbar, select **Crop** mode.



2. To zoom in or out on the content, click to select the content on the canvas and drag the **Scale** slider in the properties.
3. To position the content in the frame, click and drag on the content on the canvas.


Zoom in on Sections in Your Video

To zoom in on the content for a section in your video, add a custom animation.

1. Select **Animations** tab > **Animations** subtab, and drag the **Custom** animation onto your content on the timeline.
2. In the properties, drag the **Scale** slider to zoom in on your content. This sets the display for the end of the animation.
3. On the timeline, drag the end of the animation arrow out to slow down the animation or to speed up the animation.

Edit an Effect or Filter Applied in Rev

1. Click to expand the effects tray on the media on the timeline.



2. Click to select the effect or filter to edit.



3. Edit the options available for the effect or filter in the Properties panel. You can preview the changes on the canvas.
4. To preview the effect or filter enabled or turned off, click the effect toggle in the properties.
5. To delete the effect or filter, click the  button in the properties or press the **Delete** key.

Add a Title

Add a title or text to introduce your video, a speaker, or a scene. Learn how to create your own title or add one of our 100 million customizable and creative assets available in Camtasia, see [Enhance Your Video with Camtasia Assets \(https://www.techsmith.com/learn/?post_type=tutorial&p=246837\)](https://www.techsmith.com/learn/?post_type=tutorial&p=246837).

Edit the Background

You can customize the dynamic backgrounds applied in Camtasia Rev.

1. Click to select the background on the timeline.
2. In the Properties panel, customize the properties such as color, speed, and more. To learn more, see [Add a Dynamic Background \(https://www.techsmith.com/learn/?post_type=tutorial&p=238639\)](https://www.techsmith.com/learn/?post_type=tutorial&p=238639).

Access Your Original Recording


Camtasia maintains your original recording streams (audio, screen recording, and camera) in the Media Bin without the Camtasia Rev enhancements and effects applied.

To replace the Camtasia Rev edits with your original recording in a video:

1. Control+click (Windows) or Command+click (Mac) to select the media on the timeline and press the **Delete** key.
2. Select **Media tab > Media Bin subtab**.
3. Drag the original recording file from the Media Bin onto the timeline.

Export & Share

When you are ready to export or share your video, click the **Export** button in the upper-right corner of Camtasia Editor, then select a destination. See [Export & Share Your Video \(https://www.techsmith.com/learn/?post_type=tutorial&p=182298\)](https://www.techsmith.com/learn/?post_type=tutorial&p=182298).




Export & Share Your Video

Learn to export your project as a video file onto your computer or share to popular web destinations.

Export Overview

Export a video file based on the media on the timeline in your Camtasia project. The **Export** menu contains settings optimized to share videos to your local hard drive, Screencast, YouTube, and more.

Click **Export** and select an option from the dropdown:




Export a Video to Your Computer

The **Local File** option is best for exporting a MP4, GIF, M4A, or a video with [interactive features](https://www.techsmith.com/learn/?post_type=tutorial&p=182313) (such as [table of contents](https://www.techsmith.com/learn/?post_type=tutorial&p=182313) (https://www.techsmith.com/learn/?post_type=tutorial&p=182313), [captions](https://www.techsmith.com/learn/?post_type=tutorial&p=182326) (https://www.techsmith.com/learn/?post_type=tutorial&p=182326), [search](https://www.techsmith.com/learn/?post_type=tutorial&p=182328), [quizzing](https://www.techsmith.com/learn/?post_type=tutorial&p=182328) (https://www.techsmith.com/learn/?post_type=tutorial&p=182328), and [hotspots](https://www.techsmith.com/learn/?post_type=tutorial&p=182327) (https://www.techsmith.com/learn/?post_type=tutorial&p=182327)) onto your computer. Then, upload to a video hosting site, your channel, or social media to share the video with others.

1. Select **Export > Local File**.
2. The Export Local File dialog appears. Customize the export options:

- **Windows:** Select an option from the **Preset** dropdown or select **Custom** to edit the export settings.



- **Mac:** Select a file format from the dropdown and click the **Options** button to customize the advanced settings.

3. Click **Export**.

Tip: Batch export multiple videos.


Select **Export > Batch Export button** to quickly export a series of videos to repurpose the content to fit various platforms, video styles, or export quality requirements. See [Batch Export Videos \(https://www.techsmith.com/learn/tutorials/camtasia/batch-export/\)](https://www.techsmith.com/learn/tutorials/camtasia/batch-export/).

Export a Selection on the Timeline

Export a selection on the timeline to create a short video or to preview an effect.

▼ Learn how to export a timeline selection

1. Drag the green and red playhead handles to make a selection on the timeline.



2. Export the selection:

- **Windows:**

1. Right-click the selection and select **Export Timeline Selection As**.
2. The **Export Selection** dialog appears. Choose the desired options. If the selection includes interactive features, select the **Export with Smart Player** preset or file format. See [Export Videos with Interactive Features](#).
3. Click **Export**.

- **Mac:**

1. Select **Export > Local File**.
2. A confirmation window appears. Click **Continue** to export only the selected portion of the timeline.
3. The export dialog appears. Choose the desired options. If the selection includes interactive features, see [Export Videos with Interactive Features](#).

3. Click **Export**.

Export to Screencast

Upload your videos to Screencast to share with your audience. [Screencast](#) (<https://www.techsmith.com/screencast.html>) is a cloud-based solution for collaboration and feedback.

Your TechSmith account automatically gives you access to store up to 25 videos on Screencast for free. Or subscribe to Screencast Pro to upload unlimited videos and access additional features. Learn more about our [Screencast account tiers](#) (<https://www.techsmith.com/screencast.html>).

Check out some of the benefits of sharing your content to Screencast:

- **Supports Interactive Features**

Screencast supports any [interactive features](#) you have included in your video, such as [table of contents](#) (https://www.techsmith.com/learn/?post_type=tutorial&p=182313), [captions](#) (https://www.techsmith.com/learn/?post_type=tutorial&p=182326), [search](#), [quizzing](#) (https://www.techsmith.com/learn/?post_type=tutorial&p=182328), and [hotspots](#) (https://www.techsmith.com/learn/?post_type=tutorial&p=182327).

- **AI-Assisted Titles, Descriptions, and Chapters** ([Screencast Pro](#) (<https://www.techsmith.com/screencast.html>))

Save time and use AI-generated titles, descriptions, and video chapters for your content. See [Set Context](#)

Quickly with [AI-Assisted Titles and Descriptions \(https://www.techsmith.com/learn/tutorials/screencast/ai-generation-screencast/\)](https://www.techsmith.com/learn/tutorials/screencast/ai-generation-screencast/) and [Add Video Chapters \(https://www.techsmith.com/learn/tutorials/screencast/video-toc/\)](https://www.techsmith.com/learn/tutorials/screencast/video-toc/).

- **Auto-Generate Captions for all Videos (Screencast Pro (https://www.techsmith.com/screencast.html))**
Make your videos more accessible and easy-to-follow with AI-generated captions. For [Screencast Pro accounts \(https://www.techsmith.com/screencast.html\)](https://www.techsmith.com/screencast.html), captions are automatically generated based on the audio transcription for any videos uploaded to Screencast. See [Add Captions in Screencast \(https://www.techsmith.com/learn/tutorials/screencast/generate-captions/\)](https://www.techsmith.com/learn/tutorials/screencast/generate-captions/).
- **Conversations & Reactions**
Post a question to prompt feedback. Leave comments, annotations, and emojis on images or at specific times in a video. Your viewers can engage with your content without setting up an account. See [Manage Conversations \(https://www.techsmith.com/learn/tutorials/screencast/manage-conversations/\)](https://www.techsmith.com/learn/tutorials/screencast/manage-conversations/).

▼ Learn how to export to Screencast

Note: You must have Camtasia Windows version 2022.4.0 or later or Camtasia Mac version 2023.0.0 or later installed.

1. In Camtasia, select **Export > Screencast**.
2. The Export to Screencast dialog appears. Enter a title and optional description.
3. Click the **Export** button.
Camtasia uploads the video to your [Screencast Library \(http://app.screencast.com/\)](http://app.screencast.com/).



Export to YouTube

Upload your videos directly from Camtasia to YouTube.

Note: Recommended YouTube video resolutions vary. 720p or 1080p (HD) are best for playback on standard monitors.

▼ Learn how to export to YouTube

1. Click **Export > YouTube**. You may be asked to sign in to your YouTube account.
2. Enter a title, description, tags, privacy, and category.



Tip: Add tags to improve search engine optimization (SEO).

Add keywords from your content as tags so YouTube can help users find your video.

3. Set the privacy settings to the desired level.
4. Click **Export**.

Note: If your timeline includes captions or a table of contents:

- o **Windows:** Camtasia 2022.1.0 and later automatically uploads your captions and TOC to YouTube.
- o **Mac:** Select **Create table of contents from markers** to upload your TOC. Camtasia automatically uploads your captions to Youtube.

Camtasia uploads the video to YouTube and opens the video in a browser window for playback.

Note: Quizzes and interactive hotspots in Camtasia are not supported on YouTube.

Export Videos with Interactive Features

The TechSmith Smart Player is required for videos with interactive features such as [table of contents](https://www.techsmith.com/learn/?post_type=tutorial&p=182313) (https://www.techsmith.com/learn/?post_type=tutorial&p=182313), [captions](https://www.techsmith.com/learn/?post_type=tutorial&p=182326) (https://www.techsmith.com/learn/?post_type=tutorial&p=182326), [search](https://www.techsmith.com/learn/?post_type=tutorial&p=182328), [quizzing](https://www.techsmith.com/learn/?post_type=tutorial&p=182328) (https://www.techsmith.com/learn/?post_type=tutorial&p=182328), and [hotspots](https://www.techsmith.com/learn/?post_type=tutorial&p=182327) (https://www.techsmith.com/learn/?post_type=tutorial&p=182327).

▼ Learn how to export with the TechSmith Smart Player

To include the TechSmith Smart Player, export to any of the following options:

- **Local File (Windows):** Select the **MP4 with Smart Player** preset or file type option. On the Smart Player tab, select from these additional options:
 - To report quiz results with SCORM, enable the **Report using SCORM** option and click the **SCORM Options** button.
 - Exported vs. Hosted Smart Player Files:
For additional details about Exported vs Hosted Smart Player files, see [Hosted TechSmith Smart Player FAQ](https://support.techsmith.com/hc/en-us/articles/360048411192) (<https://support.techsmith.com/hc/en-us/articles/360048411192>).
 - **Export Smart Player files for hosting:** The export includes additional CSS and JavaScript files required to run the Smart Player on your website. As web browsers evolve, it may be necessary to manually update or reproduce video files with the newest version of Smart Player.
 - **Use hosted Smart Player files (Recommended):** Smart Player CSS and JavaScript files are hosted and kept up-to-date by TechSmith. This option ensures you always have the latest version of Smart Player without having to manually update files on your web server or reproduce video files.
- **Local File (Mac):** Select the Export to MP4 file format and enable the desired interactive options in the export dialog:
 - For captions, select an option from the **Caption Style** dropdown.
 - To include a quiz, enable the **Include Quiz** option and click **Options** to edit the settings.
 - To report quiz results with SCORM, enable the **Include SCORM** option and click **Options** to edit the settings.
 - To include a video TOC and search, enable the **Create table of contents from markers** option.
- [Screencast](#)

Tip: Archive your finished project in a folder that contains all the media in your video.

- Windows: Select **File > Export > Zipped Project**.
- Mac: Select **File > Save As** and select the **Create standalone project** option.

Enhance Your Video with Camtasia Assets

Learn how to take your video to the next level with our royalty-free online assets.


Camtasia Assets Overview

Assets are now easier than ever to access and add to your projects. You can browse over 100 million professional, royalty-free video assets directly in Camtasia. Add polish to your video with photos, videos, audio, and customizable digital content, without ever leaving the Camtasia Editor.

If you are starting with a blank Camtasia project, browse our premade assets for inspiration, such as adding a title to introduce your video or a music track to set the tone.


1. Find Camtasia Assets

1. To access the free and premium assets in Camtasia version 2023.3.0 and later, select **Media tab > Camtasia Assets subtab**.




Note: To learn how to download assets in Camtasia version 2023.2.0 and earlier, see [Find Camtasia Assets on the Website \(http://techsmith.com/learn/tutorials/camtasia/install-assets/\)](http://techsmith.com/learn/tutorials/camtasia/install-assets/) tutorial.


2. Complete any of the following:
 - Browse the assets in each category. Click **See All** to view additional assets within that category.



- o Enter a search term into the **Search** field and press the **Enter** key.



- o Click the **Search Filter** dropdown to filter the results by free assets, safe search, or your recent searches.



3. Double-click to preview an asset.

2. Add Camtasia Assets to Your Video

To add an asset to your video, drag the asset from the **Camtasia Assets** subtab onto the desired location on the timeline or canvas.

To learn how to position media on the canvas or timeline, see [Position Media on the Canvas](https://www.techsmith.com/learn/tutorials/camtasia/working-with-the-canvas/) (<https://www.techsmith.com/learn/tutorials/camtasia/working-with-the-canvas/>) and [Explore the Timeline](https://www.techsmith.com/learn/tutorials/camtasia/video-editing/) (<https://www.techsmith.com/learn/tutorials/camtasia/video-editing/>).

3. Customize Assets

After you add an asset from the **Camtasia Assets** subtab or from your personal [library](https://www.techsmith.com/learn/tutorials/camtasia/library/) (<https://www.techsmith.com/learn/tutorials/camtasia/library/>), customize the properties to:


- Edit the text.
- Match your brand colors and logos.
- Set the aesthetics or video tone.
- Get the desired effect by changing the speed or other visual properties.

To customize an asset:

1. Click to select the asset on the timeline or canvas.
2. Click the **Properties** button.



3. The Properties panel opens. Each asset has its own unique set of customizable properties, such as color, size, text, and speed. Edit the desired properties for each.



- To preview the changes, drag the playhead on the timeline to the desired start location and click the **Play** button or press the **Spacebar**. The canvas displays a preview of your video.

Camtasia Asset Types

The following asset types are available directly in Camtasia from the Camtasia Assets subtab. Some assets ([templates](https://www.techsmith.com/learn/tutorials/camtasia/use-a-template/) (<https://www.techsmith.com/learn/tutorials/camtasia/use-a-template/>), [themes](https://www.techsmith.com/learn/tutorials/camtasia/themes/) (<https://www.techsmith.com/learn/tutorials/camtasia/themes/>), and [device frames](https://www.techsmith.com/learn/tutorials/camtasia/device-frames/) (<https://www.techsmith.com/learn/tutorials/camtasia/device-frames/>)) are accessed through other locations in Camtasia and their in-product locations are noted below.

▼ Customizable

- **Titles**

Capture the attention of your viewers with the perfect title animation. Easily add your logo, text, and colors to make it your own.

- **Dynamic Backgrounds**

Looping background animations for your next project. Customize speed, color, skew, and more. See [Add a Dynamic Background](https://www.techsmith.com/learn/tutorials/camtasia/dynamic-backgrounds/) (<https://www.techsmith.com/learn/tutorials/camtasia/dynamic-backgrounds/>).

- **Motion Graphics**

Get your point across with ease. Choose from hundreds of motion graphics, like lower thirds, [callouts](https://www.techsmith.com/learn/tutorials/camtasia/annotations/) (<https://www.techsmith.com/learn/tutorials/camtasia/annotations/>), animations, and more to create powerful explainer and product videos.

- **Callouts**

Annotations, animations, and customizable graphics designed to focus viewer attention: arrows, indicators, shapes, and more. See [Add Arrows, Shapes, and Callouts](https://www.techsmith.com/learn/tutorials/camtasia/annotations/) (<https://www.techsmith.com/learn/tutorials/camtasia/annotations/>).

- **Templates**

Create video faster than ever with drag and drop video templates you can customize in just a few clicks. See [How to Use a Template](https://www.techsmith.com/learn/tutorials/camtasia/use-a-template/) (<https://www.techsmith.com/learn/tutorials/camtasia/use-a-template/>).

- **Asset Packs**

Themed video elements thoughtfully curated to help you accomplish your goals.

- **Themes**

Customizable themes instantly make your video look more professional and polished with coordinated colors and fonts. No graphic design experience necessary! See [Build Your Color Palette \(Themes\)](https://www.techsmith.com/learn/tutorials/camtasia/themes/) (<https://www.techsmith.com/learn/tutorials/camtasia/themes/>).

- **Device Frames**

Quickly make any video look like it's playing on a desktop, laptop, or mobile device screen. Establish context and add a level of professionalism to your videos with customizable device frames.

Note: To access device frames in Camtasia, select **Visual Effects** tab and drag the **Device Frame** effect onto media on the timeline. Click the **Properties** button and select the desired device frame from the **Type** dropdown. See [Provide Context with Device Frames](https://www.techsmith.com/learn/tutorials/camtasia/device-frames/) (<https://www.techsmith.com/learn/tutorials/camtasia/device-frames/>).

▼ Videos

- **Footage**

Enhance your video projects with royalty-free footage. Explore millions of high-quality video clips that bring your stories to life.

- **Animations**

These fun and expressive animations help you convey emotion, simplify complex ideas, and will delight your viewers.

- **Motion Backgrounds**

Make your videos pop with animated, looping video backgrounds. Explore millions of royalty-free motion backgrounds.

- **Effects**

Find the perfect video effect to improve your next video. Video effects library of royalty-free, short clips with an alpha channel.

▼ Images

- **Photos**

Bring your ideas to life with stunning, royalty-free photos.

- **Icons**

Discover the perfect royalty-free illustrations and icons for your next video project.

▼ Audio

- **Music**

Find high-quality background music for videos. Explore royalty-free instrumental and vocal audio tracks in various moods, styles, and genres.

- **Sound Effects**

Emphasize important content in your video with sound effects. Find the perfect royalty-free sound effect to accompany the action on screen.

Get Inspired

Check out these tutorials to continue build your skills and discover new ways to use Camtasia assets in your videos:


- [4 Ways to Visualize Your Audio](https://www.techsmith.com/learn/tutorials/camtasia/audio-visualizers/)
(<https://www.techsmith.com/learn/tutorials/camtasia/audio-visualizers/>)
- [Add a Dynamic Background](https://www.techsmith.com/learn/tutorials/camtasia/dynamic-backgrounds/)
(<https://www.techsmith.com/learn/tutorials/camtasia/dynamic-backgrounds/>)
- [Build Your Color Palette \(Themes\)](https://www.techsmith.com/learn/tutorials/camtasia/themes/)
(<https://www.techsmith.com/learn/tutorials/camtasia/themes/>)
- [Add Text to Your Video](https://www.techsmith.com/learn/tutorials/camtasia/video-text/)
(<https://www.techsmith.com/learn/tutorials/camtasia/video-text/>)
- [Set the Tone with Background Music](https://www.techsmith.com/learn/tutorials/camtasia/background-music/)
(<https://www.techsmith.com/learn/tutorials/camtasia/background-music/>)
- [Provide Context with Device Frames](https://www.techsmith.com/learn/tutorials/camtasia/device-frames/)
(<https://www.techsmith.com/learn/tutorials/camtasia/device-frames/>)
- [How to Use a Template](https://www.techsmith.com/learn/tutorials/camtasia/use-a-template/)
(<https://www.techsmith.com/learn/tutorials/camtasia/use-a-template/>)
- [Create Custom Assets](https://www.techsmith.com/learn/tutorials/camtasia/create-custom-assets/)
(<https://www.techsmith.com/learn/tutorials/camtasia/create-custom-assets/>)

Import & Manage Your Project Media (Media Bin)

Import and manage recordings, video, audio, and image source files for your current project in the Media Bin.

Media Bin Overview

The Media Bin contains any media you record or add to your current video project. To open, select **Media tab > Media Bin subtab**.



Record or Import Media into a Project

Select any of the following options to record or import content into the Media Bin to use in your video:

▼ Record the Screen

See [Build Your First Video \(https://www.techsmith.com/learn/tutorials/camtasia/record-edit-share/\)](https://www.techsmith.com/learn/tutorials/camtasia/record-edit-share/).

▼ Import Media from Your Computer

1. Click the **Media** tab.
2. Click **+** > **Import Media** or double-click in the Media Bin.
3. Click to select the media to import. **Control+click** (Windows) or **Command+click** (Mac) to select multiple files.
4. Click **Open** (Windows) or **Import** (Mac).

The imported media appears in the Media Bin.

▼ Record a PowerPoint Presentation

See [Record a PowerPoint Presentation \(https://www.techsmith.com/learn/tutorials/camtasia/record-a-powerpoint-presentation/\)](https://www.techsmith.com/learn/tutorials/camtasia/record-a-powerpoint-presentation/).

▼ Import PowerPoint Slides

See [Import PowerPoint Slides \(https://www.techsmith.com/learn/tutorials/camtasia/import-powerpoint-slides/\)](https://www.techsmith.com/learn/tutorials/camtasia/import-powerpoint-slides/).

▼ Import Media into Camtasia Rev to Apply Quick Layouts & Effects

Import a recording or footage from others into Camtasia Rev to apply a consistent look and layout in your video. See [Apply Quick Layouts & Effects with Camtasia Rev \(https://www.techsmith.com/learn/tutorials/camtasia/import-to-camtasia-rev/\)](https://www.techsmith.com/learn/tutorials/camtasia/import-to-camtasia-rev/).

▼ Record an iOS Device

See [Record an iOS Demo or Tutorial \(https://www.techsmith.com/learn/tutorials/camtasia/recording-your-ios-device/\)](https://www.techsmith.com/learn/tutorials/camtasia/recording-your-ios-device/).

▼ Import Media from a Mobile Device

Send images or videos to Camtasia from your mobile device.

1. Select **File > Connect to Mobile Device**.
2. Follow the onscreen instructions in the Connect Mobile Device dialog.

The imported media appears in the Media Bin. See [Record an iOS Demo or Tutorial \(https://www.techsmith.com/learn/tutorials/camtasia/recording-your-ios-device/\)](https://www.techsmith.com/learn/tutorials/camtasia/recording-your-ios-device/).

▼ Import Media from Google Drive

1. Click the **Media** tab.
2. Click  icon > **Import From Google Drive**.
3. Enter your Google email and password.
4. Click to select the media to import. **Control+click** (Windows) or **Command+click** (Mac) to select multiple files.
5. Click **Import**.

The imported media appears in the Media Bin.

▼ Record Voice Narration

See [Record Voice Narration](https://www.techsmith.com/learn/tutorials/camtasia/record-voice-narration/) (Camtasia Editor) or [Record a Voice-Over](https://www.techsmith.com/learn/tutorials/audiate/record-a-voice-over/) (Camtasia Audiate).

Add Media to Your Video


To include the media in your video, select **Media tab > Media Bin subtab**. Drag the media onto the desired location on the timeline or canvas.

Get tips on how to position media or assets.

See [Position Media on Canvas](https://www.techsmith.com/learn/tutorials/camtasia/working-with-the-canvas/) or [Explore the Timeline](https://www.techsmith.com/learn/?post_type=tutorial&p=182300) to get recommendations on how to position media on the canvas or timeline.

Manage & Organize Media


After adding media to your project, the following tasks help you view and organize content in the Media Bin.

Change Media Bin View	<p>Click the Media Bin View button to change the media display to one of the following options:</p>  <ul style="list-style-type: none">• Large Thumbnails• Medium Thumbnails• Small Thumbnails• Extra Small Thumbnails• List View
Sort Media	<p>Select an option from the Sort by dropdown. Click the Ascending or Descending button.</p> 

View Media Details	Right-click media and select Details .
Locate Unused Media (Media not located on the timeline)	<p>To remove unused media, right-click in the Media Bin and select Delete Unused Media.</p> <p>To select unused media, right-click in the Media Bin and select Select Unused Media.</p>
Create a Proxy Video	<p>Create a proxy of your high definition videos to improve editing performance such as lags or skips during playback.</p> <p>Right-click media in the Media Bin and select Proxy Video > Create Proxy Video. An icon appears in the video thumbnail when the process is complete.</p> 
Delete a Proxy Video	<p>Right-click (Windows) or Control+click (Mac) the proxy media in the Media Bin and select Proxy Video > Delete Proxy Video.</p> <p>To delete all proxy videos:</p> <ul style="list-style-type: none"> • Windows: Select Edit > Preferences > Advanced tab > Delete Proxy Videos button. • Mac: Select Camtasia 2023 > Settings (macOS 13 or later) or Preferences (macOS 12 or earlier) > General tab > Delete All Proxy Videos button.
Rename Media (Mac Only)	Right-click media and select Rename . Type a new name.

Create a Reverse Video

Create a copy of your video media where the events are in reversed order.



Right-click (Windows) or Control+click (Mac) the media in the Media Bin and select **Reverse Video**.

The new media is added to the Media Bin.

Note: Reversed videos do not include audio.

To cancel a reverse video while processing, right-click (Windows) or Control+click (Mac) the media in the Media Bin and select **Cancel Reverse Video**.

Camtasia Supported File Formats

Windows	Mac
Video Files AVI, MP4, MPG, MPEG, MTS, M2TS, WMV, MOV	Video Files MP4, MPG, MPEG, MOV
Camtasia Recording Files TREC	Camtasia Recording Files TREC
Image Files BMP, GIF, JPG, JPEG, PNG, PDF, TIF, TIFF, JSON (Lottie)	Image Files BMP, GIF, JPG, JPEG, PNG, PDF, JSON (Lottie)
Audio Files WAV, MP3, WMA, M4A	Audio Files M4A, WAV, MP3

Record & Edit Camera Video (Picture-in-Picture)


Learn how to record video from a webcam or other camera device to connect with your viewers. Select a layout and edit how your camera recording appears in your video.

1. Record your Screen and Camera Together

1. Complete one of the following to open the Camtasia Recorder:
 - From the Camtasia Home screen, click **New Recording Camtasia Rev.**




- From an open project, click **Record**.




2. In the Camtasia Recorder, click the **Screen Recording, Camera, Microphone, and System Audio** (optional) toggle buttons to turn them on.



3. Camtasia highlights the selected recording area on the screen. Drag the handles to adjust the selection. For more information about selecting the recording area, see [Build Your First Video \(https://www.techsmith.com/learn/tutorials/camtasia/record-edit-share/\)](https://www.techsmith.com/learn/tutorials/camtasia/record-edit-share/).
4. Click the **Camera** and **Microphone** dropdowns to select specific devices.



5. Drag the microphone slider to increase or decrease the audio level.



6. Click the **Camtasia Rev** toggle to turn on Camtasia Rev.



7. Click the **Record** button.

8. When you are finished recording, click the **Stop** button.

2. Edit Layout and Style with Rev

Your recording opens in Camtasia Rev where you can implement your own personal style with just a few clicks.

Size

Set the video size based on where you want to host or share the video. Rev provides size options to target standard video sizes for all your channels.

Layout

Choose from a series of layouts based on the content in your recording. Options include fullscreen camera or picture-in-picture layouts with both camera and screen recordings.

Background

Choose from a variety of colors, patterns, and animations for the background to make your content more visually engaging.

Effects

Apply multiple effects to the cursor, camera, and screen recording to draw attention or set the tone.

Filters

Apply visual filters to enhance the appearance of camera video.

Note: You can turn off some of the automatic selections in Camtasia Rev, such as backgrounds. Click to deselect the option on the **Background**, **Effects**, or **Filters** tabs.

If you are satisfied with your video, click **Export** to export your video directly from Rev.

Click the **Edit in Camtasia** button to further customize and edit your recording. See [Move and Resize Camera Recording](#).

3. Move and Resize Camera Recording

Camtasia Editor opens with components of your video on separate tracks:

- Background (if selected in Camtasia Rev)
- Screen recording and system audio combined
- Camera and microphone recording combined

Complete any of the following options to edit the appearance of your camera recording.

Position and Resize Camera Recording

You can further customize your content in the Rev layout you selected. For example, move your webcam to display on the left instead of the right in your video.

1. In the Canvas toolbar, select **Edit** mode.



2. To move the camera recording, click and drag the content to the desired location on the canvas.
3. To resize the camera recording, click to select the content on the canvas. Drag a corner handle in or out on the canvas or drag the **Scale** slider in the properties.

Frame Content

Camtasia Rev automatically positions your camera recording in a frame within the selected layout. To edit how your camera recording appears in the frame:

1. In the Canvas toolbar, select **Crop** mode.



2. To zoom in or out on the content, click to select the camera recording on the canvas and drag the **Scale** slider in the properties.
3. To position the content in the frame, click and drag the camera recording on the canvas.


4. Add Animations to Move or Transition Media

Add animations to media, for example to:


- Resize the camera video to fill the screen at the start of the video.
- Reposition the camera video during the video to reveal an area of the screen recording.

To add an animation:


1. Click the **Animations** tab.
2. Click the **Animations** subtab (Windows only).
3. Drag the **Custom** animation onto the camera recording on the timeline.




4. An arrow appears on the timeline. The playhead automatically moves to the head of the arrow, which indicates where the animation ends.




5. In the properties panel or on the canvas, adjust the position and scale of the camera recording for the end of the animation.



6. Optional: Move the playhead to the tail of the arrow and adjust the position and scale of the camera recording for the beginning of the animation.
7. Drag the arrow tail on the timeline to where you want the animation to start.



8. Drag the arrow head on the timeline to where you want the animation to end.
9. Drag the playhead over the animation on the timeline to review it. Make further adjustments as needed.



For detailed information about how to apply animations, see [Animations In-Depth](https://www.techsmith.com/learn/tutorials/camtasia/animations-in-depth/) (<https://www.techsmith.com/learn/tutorials/camtasia/animations-in-depth/>).

Record an iOS Demo or Tutorial

Learn how to record the screen of an iPhone or iPad and edit in Camtasia. Add gesture effects to show every tap, pinch, and swipe.

Record your iOS device screen, for example to demonstrate a mobile app. Then edit in either Camtasia for Mac or Windows and add mobile-specific gesture effects and device frames.


Record with Camtasia (Mac only)

Note: Only Camtasia for Mac supports recording iOS devices directly in Camtasia. To record and edit iOS recordings with Camtasia for Windows, see [Record with the Capture Mobile App](#).

1. Connect your iPhone or iPad with a Lightning or USB-C cable to a computer running Snagit for Mac.



2. In Camtasia, select **File > New Recording**.
3. Camtasia Recorder opens. Click the **Screen** dropdown and select the iOS device from the Mobile Device section.



Note: A message appears if you must update the macOS to a newer version to record your mobile device.

To learn how to set up the other recording options such as microphone or system audio, see [Build Your First Video \(https://www.techsmith.com/learn/tutorials/camtasia/record-edit-share/\)](https://www.techsmith.com/learn/tutorials/camtasia/record-edit-share/).

4. Set up the desired screen on your device and click the **Start Recording** button in Camtasia.
5. When you are finished recording the iOS device, click the **Stop Recording** button in Camtasia.

The recording opens in Camtasia Editor. Add [gesture effects](#) or a [device frame](#) to enhance your final video.

Record with the Capture Mobile App


The TechSmith Capture mobile app offers a cable-free way to record your iOS device and send the file to Camtasia. Use this option:

- When you can't connect your iOS device to your computer with a cable.
- To record on an iOS device and send the recording to Camtasia for Windows or Mac.


Note: Your iOS device and computer must be connected to the same wireless network.

To record with the Capture mobile app and export to Camtasia:

1. On your iPhone or iPad, download the TechSmith Capture mobile app from the [App Store \(https://apps.apple.com/us/app/techsmith-capture/id1266321056\)](https://apps.apple.com/us/app/techsmith-capture/id1266321056).
2. Open the Capture mobile app and sign in to your TechSmith account.
3. Tap the red **Record** button.



4. Tap the **Microphone** button to turn microphone recording on or off.
5. When you are ready to start, tap **Start Broadcast**.
6. Capture shows a three-second countdown, then begins recording. During recording, a red indicator appears on the screen.
7. To stop recording, tap the **recording indicator**, then tap **Stop**.



8. Tap the notification at the top of the screen to view the recording in the Capture mobile app.
9. Tap **Share**.
10. In the Export dialog, tap **Camtasia**.
11. Complete one of the following, depending on the situation:
 - If you have not yet connected your mobile device to Camtasia, follow the instructions on the screen.
 - If you previously connected your iOS device to Camtasia, your recording is automatically added to the Camtasia Media Bin.
 - If you have connected your iOS device to multiple versions of Camtasia, tap to select the version you want to send to.

Your recording is added to the Camtasia Media Bin.

Note: If Capture is unable to export to Camtasia see:

- [TechSmith Capture \(iOS\) App Troubleshooting \(https://support.techsmith.com/hc/en-us/articles/360016417072-TechSmith-Capture-iOS-App-Troubleshooting\)](https://support.techsmith.com/hc/en-us/articles/360016417072-TechSmith-Capture-iOS-App-Troubleshooting)
- [Alternative ways to send to Camtasia](#)

Alternative Ways to Send to Camtasia

If Capture cannot export directly to Camtasia, transfer the recording to your computer via AirDrop (Mac only) or a cloud-based storage service such as Dropbox or Google Drive. Then import it manually to Camtasia.

▼ View AirDrop steps (Mac only)

1. Open the recording in the Capture mobile app.
2. Tap **Share**.
3. In the Export dialog, tap **More**.
4. In the Share dialog, tap **AirDrop**.
5. In the AirDrop dialog, tap to select the name or serial number of the Mac computer.
6. In the AirDrop notification on your Mac computer, select **Accept > Save to Downloads**.
7. Import the media file to your Camtasia project. See [Import & Manage Your Project Media \(Media Bin\)](https://www.techsmith.com/learn/tutorials/camtasia/import-manage-media/) (<https://www.techsmith.com/learn/tutorials/camtasia/import-manage-media/>).

▼ View cloud-based storage steps (Mac or Windows)

1. Open the recording in the Capture mobile app.
2. Tap **Share**.
3. In the Export dialog, tap **More**.
4. In the Share dialog, tap to select a cloud-based storage app, or tap **More** and then select the app.
5. Select a location for the file and tap **Upload**.
6. Import the media file to your Camtasia project. See [Import & Manage Your Project Media \(Media Bin\)](https://www.techsmith.com/learn/tutorials/camtasia/import-manage-media/) (<https://www.techsmith.com/learn/tutorials/camtasia/import-manage-media/>).


Add Gesture Effects

Gesture effects add visual effects that simulate taps, swipes, and pinches on mobile devices.

1. Click the **Gesture Effects** tab.
2. Drag a gesture effect onto the canvas.
3. To change the duration of an effect, click the **Show Effects** tab on the timeline and drag the ends of the effect in or out.




4. To edit the properties, click to select the effect on the timeline and edit the settings in the Properties panel.



Add a Device Frame

Add a device frame around an image or video clip to provide context or to position a vertical recording within a horizontal video.

To learn how to add a device frame, see [Provide Context with Device Frames \(https://www.techsmith.com/learn/tutorials/camtasia/device-frames/\)](https://www.techsmith.com/learn/tutorials/camtasia/device-frames/).



How to Use a Template

Learn how to use templates to create consistent looking videos for yourself or your teammates.

Templates include placeholders for your video clips and make it easier to create:


- Polished videos without starting from scratch.
- Consistent videos for yourself and your team.

Choose from professionally-designed templates available in Camtasia or from the [Camtasia Assets website \(https://library.techsmith.com/en/camtasia/Customizable\)](https://library.techsmith.com/en/camtasia/Customizable), or [build a video template to share \(https://www.techsmith.com/learn/tutorials/camtasia/create-a-template/\)](https://www.techsmith.com/learn/tutorials/camtasia/create-a-template/).

Create a Video Project from a Template


1. In Camtasia Editor, select **File > New Project from Template**.
2. The Template Manager opens. Select a template and click **New from Template**.

Note: Some templates are designed to swap in images rather than video. To find a template designed specifically for video content, look for “This is your scene” in the template thumbnail or preview.




3. The template opens as a new project. Select **File > Save As** to save the video project file (.tscproj for Windows or .cmproj for Mac).
4. If the placeholder is in a group, click the **+** icon on the timeline to open the group. Media within the group appear on separate tracks, and the group name displays in a tab above the timeline. To learn more, see [How](#)


to Use Group Tabs (<https://www.techsmith.com/learn/tutorials/camtasia/grouped-media/>).



5. To replace video content in a template, select the **Media** tab and drag a recording from the [Media Bin](https://www.techsmith.com/learn/tutorials/camtasia/import-manage-media/) (<https://www.techsmith.com/learn/tutorials/camtasia/import-manage-media/>), [Assets](https://www.techsmith.com/learn/tutorials/camtasia/camtasia-assets/) (<https://www.techsmith.com/learn/tutorials/camtasia/camtasia-assets/>), or [Library](https://www.techsmith.com/learn/tutorials/camtasia/library/) (<https://www.techsmith.com/learn/tutorials/camtasia/library/>) subtab onto the original media or placeholder on the timeline. When a green outline appears around the media or placeholder, release your mouse button.



6. A menu appears with the replacement options. If the new media is a different duration than the media or placeholder, select one of the following options:
 - **Ripple Replace:** Shift all clips on the track to the right to insert space for the entire duration of the new media.
 - **Replace with Clip Speed:** Increase the playback speed of the new media to fit the duration of the placeholder.
 - **Replace From End:** Trim the new media to fit the duration of the placeholder. If the new media is longer, the beginning of the clip is trimmed to fit the duration.
 - **Replace From Start:** Trim the new media to fit the duration of the placeholder. If the new media is longer, the end of the clip is trimmed to fit the duration.
7. A [group](https://www.techsmith.com/learn/tutorials/camtasia/grouped-media/) (<https://www.techsmith.com/learn/tutorials/camtasia/grouped-media/>) is created with the name of the new media. If you need to adjust the scale or other media properties to fit the template:



1. Click the **+** icon to open the new media group.
 2. Select the media on the timeline.
 3. Make any necessary adjustments in the [Properties](https://www.techsmith.com/learn/tutorials/camtasia/media-properties/) panel.
 4. Click the **X** icon on the group tab above the timeline to close the group.
8. To share the video, see [Export & Share Your Video](https://www.techsmith.com/learn/tutorials/camtasia/export-share/).

Tip: Find more templates on the Camtasia Assets website.


Browse and import professionally-designed, customizable templates from the Camtasia Assets website. See [Import a Template from Camtasia Assets](#).

Manage Templates

- [Import a Template from Camtasia Assets](#)
- [Import a Template from Your Computer](#)
- [Rename a Template](#)
- [Delete a Template](#)

Import a Template from Camtasia Assets

1. In Camtasia Editor, select **File > New Project from Template**.
2. The Template Manager dialog opens. Click the **Download more Templates** button.
3. The [Camtasia Assets website](https://library.techsmith.com/en/camtasia/assets/Customizable/Templates) opens.
 - On Mac, select **Browse Assets for Camtasia > Templates**.
4. Hover your mouse over a template to show a larger preview and available options.
5. Click the **Send to Camtasia** button.



The template is added to the Template Manager dialog. The Template Manager lists all the templates currently available in Camtasia.

Import a Template from Your Computer

Import templates created by you or your team. To learn how to create your own template, see [Build a Video Template to Share \(https://www.techsmith.com/learn/tutorials/camtasia/create-a-template/\)](https://www.techsmith.com/learn/tutorials/camtasia/create-a-template/).

1. In Camtasia Editor, select **File > New Project from Template**.
2. The Template Manager dialog opens. Click the  button.
3. Select the .camtemplate file and click **Open**.

The template is added to the Template Manager dialog. The Template Manager lists all the templates currently available in Camtasia.

Rename a Template

1. In Camtasia Editor, select **File > Manage Templates** (Windows) or **Camtasia > Manage Templates** (Mac).
2. The Template Manager dialog opens. Click to select a template.
3. Click  and select **Rename Template**.
4. Type the new template name and press **Enter**.

Delete a Template

1. In Camtasia Editor, select **File > Manage Templates** (Windows) or **Camtasia > Manage Templates** (Mac).
2. The Template Manager dialog opens. Click to select a template.
3. Click  and select **Delete Template**.
4. Click **Delete** (Windows) or **Yes** (Mac) to confirm.

Apply Quick Layouts & Effects with Camtasia Rev


Learn how to import existing recordings into Camtasia Rev to create a consistent look throughout your video.

Start a New Camtasia Rev Recording

1. Open Camtasia.
2. Click **New Recording Camtasia Rev**.



3. Camtasia Recorder opens. Set up your desired recording settings. See [Build Your First Video](https://www.techsmith.com/learn/tutorials/camtasia/record-edit-share/) (<https://www.techsmith.com/learn/tutorials/camtasia/record-edit-share/>). Make sure the **Camtasia Rev** option is enabled.



4. Click the **Record** button.

After recording, a preview of the recording opens in Camtasia Rev.

1. Select the desired customizations. See [Accelerate Video Creation with Camtasia Rev Customizations](#).
2. Export your video directly from Camtasia Rev, or click **Edit in Camtasia** for further editing and enhancements. See [Basic Edits after Recording](https://www.techsmith.com/learn/tutorials/camtasia/basic-video-edits/) (<https://www.techsmith.com/learn/tutorials/camtasia/basic-video-edits/>).

Apply Rev Layouts & Effects to Imported Media in a Project

The **Import to Camtasia Rev** option helps to quickly apply a consistent look and layout across media in your video.

If you have previous Camtasia recordings or footage recorded by others, you can import the media into Camtasia Rev to apply a similar look and layout across scenes throughout your video project.

Note: Camtasia Rev supports various video, image, and audio file formats. We recommend importing an unedited Camtasia Recording file (.trec) to access all of the layouts and effects available in Camtasia Rev based on the rich recording data collected in this file format, such as camera, screen recording, and cursor data.

1. Select **Media tab > Media Bin subtab**.
2. Click the  button and select **Import Media** to add content to the Media Bin in your project.
3. Right-click (Windows) or Control-click the media in the Media Bin and select **Import to Camtasia Rev**.
4. The media opens in Camtasia Rev. Select the desired customizations. See [Accelerate Video Creation with Camtasia Rev Customizations](#).

Note: The **Size** tab is disabled if your project already contains media on the timeline. Camtasia sets the size to the current canvas dimensions in the video project.

5. Click **Edit in Camtasia** to continue editing.

Camtasia adds the Camtasia Rev media onto the timeline. To learn how to apply our recommended edits after completing your recording and enhancements in Camtasia Rev, see [Basic Edits after Recording](https://www.techsmith.com/learn/tutorials/camtasia/basic-video-edits/) (<https://www.techsmith.com/learn/tutorials/camtasia/basic-video-edits/>).

Apply Rev Layouts & Effects to Prerecorded Media

Now you can access Camtasia Rev at any time, not just from Camtasia Recorder. Open previously recorded footage and recordings in Camtasia Rev to accelerate video creation.



1. Open Camtasia.
2. Click **Import to Camtasia Rev**.

3. Select the media and click **Open**.

Note: Camtasia Rev supports various video, image, and audio file formats. We recommend importing an unedited Camtasia Recording file (.trec) to access all of the layouts and effects available in Camtasia Rev based on the rich recording data collected in this file format, such as camera, screen recording, and cursor data.

4. Camtasia Rev opens. Select the desired customizations. See [Accelerate Video Creation with Camtasia Rev Customizations](#).
5. Export your video directly from Camtasia Rev, or click **Edit in Camtasia** for further editing and enhancements. See [Basic Edits after Recording \(https://www.techsmith.com/learn/tutorials/camtasia/basic-video-edits/\)](https://www.techsmith.com/learn/tutorials/camtasia/basic-video-edits/).

Accelerate Video Creation with Camtasia Rev Customizations

Here are some customizations available in Camtasia Rev. Implement your own personal style with just a few clicks.

Size

Set the video size based on where you want to host or share the video. Rev provides size options to target standard video sizes for all your channels.

Layout

Choose from a series of layouts based on the content in your recording.

Background

Choose from a variety of colors, patterns, and animations for the background to make your content more visually engaging.

Effects

Apply multiple effects to the cursor, camera, and screen recording to draw attention or set the tone.

Filters

Apply visual filters to enhance the appearance of camera video.

Note: You can turn off some of the automatic selections in Camtasia Rev, such as backgrounds. Click to deselect the option on the **Background**, **Effects**, or **Filters** tabs.


Reuse Media Across Projects (Library)

Learn how to speed up the video creation process and maintain consistency across your videos with personal media libraries.

Library Overview

The library stores any custom assets or media you want to reuse across your Camtasia video projects. Save intros, animated backgrounds, icons, titles, music, groups, annotations, and more to your library to use consistent elements across your videos.

To open the library, select **Media tab > Library subtab**.



To add a library asset to your video, complete one of the following:

- Drag the asset from the **Library** subtab onto the desired location on the timeline.
- Right-click (Windows) or Control+click (Mac) the asset in the library and select **Add to Timeline at Playhead**.

Get tips on how to position media or assets.

See [Position Media on Canvas](https://www.techsmith.com/learn/?post_type=tutorial&p=182299) (https://www.techsmith.com/learn/?post_type=tutorial&p=182299) or [Explore the Timeline](https://www.techsmith.com/learn/?post_type=tutorial&p=182300) (https://www.techsmith.com/learn/?post_type=tutorial&p=182300) for recommendations on how to position media on the canvas or timeline.

Add or Organize Assets

Create a Custom Library

Organize assets based on a project, video type, asset type, or brand.

1. Select **Media tab > Library subtab**.
2. In the Library dropdown, select **Create New Library**.
3. Enter a name.
4. Select an option in the **Start from** dropdown to create a blank library or create a copy of an existing library.
5. Click **Create**.

Asset or Group from Timeline:

1. Right-click (Windows) or Control+click (Mac) an asset or group on the timeline and select **Add to Library**.
2. Enter a name.


Tip: Best practices when naming assets

- o Keep the name short.
- o Avoid generic names such as “callout1”. Use descriptive cues such as video purpose, asset type, or color in the name. For example, “blue-speaker-intro”.

3. Select a library from the **Library** dropdown.
4. Select **Use Canvas Size** to have the asset or group automatically resize based on the canvas dimensions or **Use Visible Size** to keep the original dimensions.
5. Click **OK**.

Selection from Timeline:

1. Click and drag the green and red handles to select an area on the timeline.




2. Right-click (Windows) or Control+click (Mac) the selection and select **Add Timeline Selection to Library**.

Add an Asset or Group to a Library

3. Enter a name.
4. Select a library from the **Library** dropdown.
5. Select **Use Canvas Size** to have the asset or group automatically resize based on the canvas dimensions or **Use Visible Size** to keep the original dimensions.
6. Click **OK**.

From Computer:

1. Select **Media tab > Library subtab**.
2. Click the + icon and select **Import Media to Library** or drag the desired assets into a library or folder.



From Media Bin:

1. Select the **Media tab > Media Bin subtab**.
2. Right-click (Windows) or Control+click (Mac) an asset in the [Media Bin](https://www.techsmith.com/learn/?post_type=tutorial&p=182296) (https://www.techsmith.com/learn/?post_type=tutorial&p=182296) and select **Add to Library**.
3. Select a library from the **Library** dropdown.
4. Click **OK**.

Add a Folder to the Library

1. Select the **Media tab > Library subtab**.
2. Select a library from the **Library** dropdown.
3. Right-click (Windows) or Control+click (Mac) within the library and select **New Folder**.
4. Enter a folder name.
5. Press the **Enter** key.


Move Assets or Folders within a Library

1. Select the **Media tab > Library subtab**.
2. Select a library from the **Library** dropdown.
3. Click to select the asset or folder. **Ctrl+click** (Windows) or **Command+click** (Mac) to select multiple assets or folders.
4. Drag the selection to the desired folder or location in the current library.

	<p>Note: To nest a folder in a library, click and drag the folder onto another folder.</p>
<p>Move Assets or Folders to Another Library</p>	<ol style="list-style-type: none"> 1. Select the Media tab > Library subtab. 2. Select a library from the Library dropdown. 3. Click to select the asset or folder. Ctrl+click (Windows) or Command+click (Mac) to select multiple assets or folders. 4. Right-click (Windows) or Control+click (Mac) the selection and select Move To > the desired library.
<p>Delete an Asset or Folder</p>	<p>Right-click (Windows) or Control+click (Mac) the asset or folder in the library and select Delete.</p>

Find Assets

Search within a library or across all libraries to find assets based on file names.

<p>Search for Assets in Library</p>	<ol style="list-style-type: none"> 1. Select the Media tab > Library subtab. 2. Click the Search icon and select the scope of the search: Search All Libraries, Search Current Library, or select a recent search term from the dropdown.  <ol style="list-style-type: none"> 3. Type in the Search Library field. 4. The search results appear. To sort the search results, right-click (Windows) or Control+click (Mac) a result and select Sort By.
<p>Sort Assets</p>	<p>Right-click (Windows) or Control+click (Mac) a folder or asset in the library and select Sort By. You can sort by name, type, date added, date used, or reverse the order.</p>
<p>Preview an Asset</p>	<p>Double-click the asset in the library. A preview window appears.</p>

Share a Library

To maintain a consistent video style across a project or organization, share your library assets with others.

Create a Camtasia Package (.campaqage) to back up and share your Camtasia resources such as [templates](https://www.techsmith.com/learn/?post_type=tutorial&p=182343) (https://www.techsmith.com/learn/?post_type=tutorial&p=182343), [shortcuts](https://www.techsmith.com/learn/?post_type=tutorial&p=182360) (https://www.techsmith.com/learn/?post_type=tutorial&p=182360), libraries, [themes](https://www.techsmith.com/learn/?post_type=tutorial&p=182345) (https://www.techsmith.com/learn/?post_type=tutorial&p=182345), and [presets](https://www.techsmith.com/learn/?post_type=tutorial&p=182310) (https://www.techsmith.com/learn/?post_type=tutorial&p=182310) to another user or computer. See [Package & Share Camtasia Resources](https://www.techsmith.com/learn/?post_type=tutorial&p=182342) (https://www.techsmith.com/learn/?post_type=tutorial&p=182342).

Note: If you upgrade from Camtasia version 2019 or later, user libraries are automatically imported into the latest version of Camtasia during installation. To import libraries from previous versions, complete the steps below.

Export a Library	<ol style="list-style-type: none">1. Select the Media tab > Library subtab.2. Select a library from the Library dropdown.3. Select Library dropdown > Manage Library > Export Library.4. Click Save to save the .libzip file.5. Send the .libzip file to others to import into Camtasia.
Import a Library	<ol style="list-style-type: none">1. Select File > Library > Import Zipped Library.2. Locate the .libzip file to import and click Open.3. Choose to create a new library or add the assets to an existing library and click Import. <p>Camtasia adds the assets to the selected library.</p>


Position Media on the Canvas

Learn how to preview and arrange media on the canvas for your video.

The canvas is the working area where you preview, arrange, rotate, resize, and order the appearance of media in your video.


Position Media

Complete any of the following edits on the canvas to position the appearance of media in your video.




Move

Click and drag media to move to a new location on the canvas.




Resize / Scale

Click to select media on canvas. Drag white media handle in or out.



Rotate

Click to select media on canvas. Drag the center handle in media to rotate around the anchor point.




Crop

1. In the Canvas toolbar, click the **Crop** button.



2. Click to select media on canvas and drag a blue handle in or out.
3. Click and drag the media to position the content within the frame.



Align

The canvas offers boundary guidelines to help you snap media to the edge, center, or align with other media.

- **Canvas Guides:** The guides appear as you drag media on the canvas. Drag media until it aligns with the edge, center, or other media guidelines.

To disable canvas snapping guidelines, select **View > Enable Canvas Snapping** to remove the checkmark.

- **Ruler Guides:** See [Align Media with Ruler Guides \(https://www.techsmith.com/learn/?post_type=tutorial&p=241938\)](https://www.techsmith.com/learn/?post_type=tutorial&p=241938).



Arrange – Timeline Z-Order

To reorder media on the canvas, right-click (Windows) or Control+click (Mac) and select **Arrange**.


The z-order position of media on the canvas is set by the placement of media on the [timeline \(https://www.techsmith.com/learn/?post_type=tutorial&p=182300\)](https://www.techsmith.com/learn/?post_type=tutorial&p=182300). Media on the top timeline track appears in front of media on lower tracks on the canvas.

Tip: Open the Properties for precise canvas edits.

Click to select the media or asset on the canvas and click the **Properties** button to view the properties available. In the Properties, you can edit text, colors, styles, and other options. See [Discover the Properties Panel \(https://www.techsmith.com/learn/?post_type=tutorial&p=182312\)](https://www.techsmith.com/learn/?post_type=tutorial&p=182312).


Canvas Editing Modes

The canvas tools are located in the toolbar above the canvas.



Tool	Description
Edit mode (Default) 	Select this mode to move, resize, and rotate media on the canvas.
Corner Pin mode 	Select this mode to create a 3D perspective or to pin the corners of the media to fit within the boundaries of another object, such as a device frame. For example, replace what's shown on a computer display with your own screen recording or simulate text on a whiteboard. See Create the Illusion of 3D Perspective (Corner Pinning) (https://www.techsmith.com/learn/tutorials/camtasia/corner-pinning/) .

Tool	Description
	
<p>Pan mode</p> 	<p>If you are zoomed in and the entire canvas is not visible, select this mode or hold the Spacebar and drag to change the visible area on the canvas.</p> <p>Camtasia keeps the original position and size when panning. Canvas editing is disabled in Pan mode.</p>
<p>Crop mode</p> 	<p>Select this mode to trim the unwanted areas from media.</p> <ol style="list-style-type: none"> 1. Click Crop to turn crop mode on. 2. Click to select the media on the canvas to crop. 3. Drag the blue handles to remove the desired area. <p>You can also hold the Alt key (Windows) or the Option key (Mac) and drag to crop media while in another mode.</p>
<p>Detach / Attach Canvas</p>	<p>To view the video preview in full screen mode or for better viewing, detach the canvas from the Camtasia application window and move it to another location, such as onto another monitor.</p> <p>To detach the canvas: Right-click (Windows) or Control+click (Mac) an empty area on the canvas and select Detach Canvas. Drag the detached canvas to the desired location on your screen.</p> <p>To reattach the canvas: Right-click (Windows) or Control+click (Mac) an empty area on the canvas and select Attach Canvas.</p>


Tool	Description
<p>Full Screen mode</p>  Windows  Mac	<p>If the canvas is detached from the Camtasia application window, you can expand the canvas to full screen mode. Press ESC to exit.</p>
<p>Change the canvas magnification</p> 	<p>To help preview or edit media in your video, you can adjust the canvas zoom level. Click the Canvas Options dropdown menu to select the zoom level.</p> <ul style="list-style-type: none"> This does not change the canvas dimensions / editing dimensions or affect the size of the final video. Select Fit to view the entire video within the boundaries of the canvas. When the view is magnified, click the Pan Mode button or hold the Spacebar and drag to change the visible area on the canvas.
Project Settings	<p>Set the canvas dimensions, editing frame rate, and audio level for your project. See Crisp and Clear Screen Recordings (https://www.techsmith.com/learn/?post_type=tutorial&p=182307).</p>

Change the Background Color

If media or assets do not cover the entire canvas, the canvas background displays in the final video.

For the entire video:

1. Right-click (Windows) or Control+click (Mac) the canvas and select **Project Settings**.
2. The Project Settings dialog appears. Select a color from the **Color** dropdown.




3. Click **Apply**.


For a portion of the video:

1. Click the **Annotations** tab.

2. Click the **Shapes** subtab.




3. Drag a rectangle onto the canvas. Drag the handles until the annotation covers the entire canvas.



4. Right-click (Windows) or Control+click (Mac) the annotation on the canvas and select **Arrange > Send to Back**.

5. In the properties, select the desired background color from the **Fill** color dropdown and the **Outline** color dropdown.

6. Drag an end of the annotation on the timeline to set the duration for the background in the video.



Edit Zoom Recordings

Bring your Zoom recording into Camtasia to remove unwanted sections, fix audio, and add polish so that it is ready to share.

Import Zoom Recording

1. Open Camtasia.
2. Click the **Media** tab.
3. Click  > **Import Media** or double-click the Media Bin.
4. Browse to select the Zoom recording and click **Open** (Windows) or **Import** (Mac).
5. The imported media appears in the Media Bin. Drag the Zoom recording from the Media Bin onto the timeline.

Tip: Save time editing with variable speed shortcuts.

- Press **J** to reverse the timeline playback at normal (1x), 2x, 4x, or 8x speed.
- Press **K** to pause the timeline playback.
- Press **L** to play the timeline forward at normal (1x), 2x, 4x, or 8x speed.

Trim the Start and End

Trim out the wait time or conversations recorded before the Zoom call content begins.

1. On the timeline, drag the end of the clip in or out.
2. Drag the playhead to the desired location on the clip and click **Play** to preview the trimmed clip.

Remove Sections

1. Click and drag the green or red handles on the playhead to make a selection.
2. Click the **Cut** button.



The selection is removed and the remaining media is stitched together.

Edit Audio


Add audio points to adjust the volume for a part of the Zoom recording.

1. On a clip with audio, double-click to add an audio point.
2. Drag an audio point or line between audio points to raise or lower the volume.

See [Edit Audio \(https://www.techsmith.com/learn/?post_type=tutorial&p=182336\)](https://www.techsmith.com/learn/?post_type=tutorial&p=182336).

Add an Intro or Outro

Intros are animations and text that provide context for the video's content. Outros are animations and text that provide resources such as contact information, a website, or a call-to-action for viewers to conclude a video.




To use one of Camtasia's premade titles for your intro or outro:

1. Select the **Media tab > Camtasia Assets subtab > Titles > See All**.
2. Browse or search for a Title asset.
3. To add an asset to your video, drag the asset from the **Camtasia Assets** subtab onto the desired location on the timeline or canvas.
4. To customize the title, click the **Properties** button. Each asset has its own unique set of customizable properties, such as color, size, text, and speed. Edit the desired properties for each.

To learn more about Camtasia Assets, see [Enhance Your Video with Camtasia Assets \(https://www.techsmith.com/learn/tutorials/camtasia/camtasia-assets/\)](https://www.techsmith.com/learn/tutorials/camtasia/camtasia-assets/).

Share Your Recording



To share your edited Zoom recording, click **Export** and select the option that works best for you.

Select **Local File** to save to your computer or share to another destination like YouTube.

See [Export & Share Your Video \(https://www.techsmith.com/learn/?post_type=tutorial&p=182298\)](https://www.techsmith.com/learn/?post_type=tutorial&p=182298) for details about sharing options.


Where Is My Camtasia Library?

Learn where to find the new location for the Camtasia library in version 2023.3.0 and later.

We moved the library to the **Media** tab so all the options to add media and assets to your video are all located in one location. See [Assemble Your Video \(https://www.techsmith.com/learn/?post_type=tutorial&p=246834\)](https://www.techsmith.com/learn/?post_type=tutorial&p=246834).

Previous Location


In Camtasia 2023.2 and earlier, the library was located on a separate tab.



New Location

In Camtasia 2023.3.0 and later, you can find the library here:

Select **Media tab > Library subtab**.



To learn about all the ways you can add content to your video, continue with these tutorials:

- [Reuse Assets Across Projects \(Library\)](https://www.techsmith.com/learn/?post_type=tutorial&p=182344) (https://www.techsmith.com/learn/?post_type=tutorial&p=182344)
- [Enhance Your Video with Camtasia Assets](https://www.techsmith.com/learn/?post_type=tutorial&p=246837) (https://www.techsmith.com/learn/?post_type=tutorial&p=246837)
- [Import & Manage Project Media \(Media Bin\)](https://www.techsmith.com/learn/?post_type=tutorial&p=182296) (https://www.techsmith.com/learn/?post_type=tutorial&p=182296)

Record a PowerPoint Presentation

Learn three ways to record a Microsoft PowerPoint presentation with Camtasia.

Camtasia provides three ways to record a Microsoft PowerPoint Presentation:

1. [Record with the Camtasia PowerPoint Add-In \(Windows\)](#)
2. [Import Slides into Camtasia and Record Voice Narration](#)
3. [Record with Camtasia Recorder](#)

Record with the Camtasia PowerPoint Add-In (Windows)


The Camtasia PowerPoint Add-In allows you to record a presentation directly in Microsoft PowerPoint. The video recording captures any transitions or animations in the presentation.

Note: The PowerPoint Add-in toolbar is only available on Windows. To record a presentation on Mac, see [Import Slides into Camtasia \(https://www.techsmith.com/learn/?post_type=tutorial&p=182346\)](https://www.techsmith.com/learn/?post_type=tutorial&p=182346) or [Record with Camtasia Recorder](#).

1. Open Microsoft PowerPoint.
2. Click the **Add-Ins** tab.
3. Select the recording options in the toolbar.



4. Click the **Record** button.
5. Test your audio and then click the button to begin recording or press **CTRL+SHIFT+F9**.



6. Press **CTRL+SHIFT+F10** or press the **ESC** key to stop recording.

7. Click the **Stop Recording** button.
8. Name the recording and click **Save**.
9. Select **Produce your recording** or **Edit your recording** and click **OK**.

To learn more about recording and customizing the PowerPoint Add-In settings, see [Record with the PowerPoint Add-In \(https://www.techsmith.com/learn/?post_type=tutorial&p=182347\)](https://www.techsmith.com/learn/?post_type=tutorial&p=182347).

Import Slides into Camtasia

Import individual .ppt or .pptx slides into the Media Bin. Drag the slides onto the timeline to build your video presentation and record voice narration to complete your video. This method allows you to add additional transitions, callouts, and other video enhancements offered in Camtasia.

See [Import PowerPoint Slides \(https://www.techsmith.com/learn/?post_type=tutorial&p=182346\)](https://www.techsmith.com/learn/?post_type=tutorial&p=182346).

Record with Camtasia Recorder

Record with Camtasia Recorder to capture the presentation as you deliver it. Open the Microsoft PowerPoint presentation in Presenter mode and record with the Camtasia Recorder. As you record, the transitions and animations in the presentation are captured in the recording.

To learn more about setting up your recording, see [Record, Edit, Share \(https://www.techsmith.com/learn/?post_type=tutorial&p=182295\)](https://www.techsmith.com/learn/?post_type=tutorial&p=182295).

Record with the PowerPoint Add-In (Windows)

Learn how to customize the Camtasia Add-In for Microsoft PowerPoint to record presentations.


The Camtasia PowerPoint Add-in provides robust, customizable options to record in Microsoft PowerPoint, and then edit or produce the recording in Camtasia.

Note: The Microsoft PowerPoint Add-In toolbar is only available for Windows. To record PowerPoint slides on Mac, see [Import PowerPoint Slides \(https://www.techsmith.com/learn/?post_type=tutorial&p=182346\)](https://www.techsmith.com/learn/?post_type=tutorial&p=182346) or [Record a PowerPoint Presentation \(https://www.techsmith.com/learn/?post_type=tutorial&p=182352\)](https://www.techsmith.com/learn/?post_type=tutorial&p=182352).


Set Up the Recording

Note: The PowerPoint add-in toolbar is installed by default with Camtasia. If the add-in does not appear in Microsoft PowerPoint, complete the following: select **File > Options > Add-ins tab > Manage dropdown**. Select **Disabled Items** and click **Go**. If the Camtasia add-in appears in the list, select it and click **Enable**.

1. Open Microsoft PowerPoint.
2. Click the **Add-Ins** tab.



3. Recording options appear in the toolbar.




4. Set the recording options:
 - o **A. Record audio:** Click to toggle microphone or system audio recording on or off. To select the device and specific audio settings, see [Camtasia Add-in Options](#).
 - o **B. Record camera:** Click to toggle camera on or off.

- o **C. Show camera preview:** Click to open a preview of the camera. Click the **X** in the top-right corner to close the preview.
- o **D. Recording options:** Click to open the [Camtasia Add-in Options](#) settings.

Camtasia Add-in Options


Click the **Recording Options** button in the toolbar to open the Camtasia Add-in Options.

Option	Description
Start recording paused	<ul style="list-style-type: none"> • Select this option to check microphone levels before recording.  <ul style="list-style-type: none"> • Deselect this option to record immediately once you click the Record button.
Edit in Camtasia when finished	<ul style="list-style-type: none"> • Select this option to automatically open Camtasia after recording. • Deselect this option to save the recording without opening Camtasia.
Include watermark	<ul style="list-style-type: none"> • Select this option to display a logo or other image in your recording. • Click Watermark to select the image and display properties.
At end of presentation	Select an option to Continue recording , Prompt to continue recording , or Stop recording .
Screen frame rate	Select the number of frames recorded per second. Recordings with higher frame rates display more smoothly but also result in larger file size.
Record to	Select TSC2 or H.264 video coding format. For guidance on which format to choose, see When to Use TSC2 vs H264 in Camtasia for Screen Recording (https://support.techsmith.com/hc/en-us/articles/360042592752-When-to-Use-TSC2-vs-H264-in-Camtasia-for-Screen-Recording).
Record audio	<ul style="list-style-type: none"> • Select to record microphone and/or system audio. • Deselect to record video only.
Audio	


source	Select a built-in or connected microphone.
Volume	Slide to adjust recording volume.
Capture system audio	Select to record the system audio (sounds from applications and websites).
Record from camera	<ul style="list-style-type: none"> • Select to record from a built-in or connected camera for Picture-in-Picture display. • Click Camera setup to preview the webcam and select the camera device, dimensions, and frame rate.
Keyboard shortcuts	Customize hotkey combinations to control Record/Pause and Stop recording.

Record the PowerPoint Presentation


1. In PowerPoint, open the Camtasia Add-in and set the recording options. See [Set Up the Recording](#).
2. Click the **Record** button.
 - If the **Start recording paused** option is not selected, recording begins immediately.
 - If the **Start recording paused** option is selected, the Camtasia Recording Paused window appears. Speak to test your audio and slide the Microphone setting to adjust volume as needed. Click the button to begin recording or press **CTRL+SHIFT+F9**.



3. Press **CTRL+SHIFT+F10** or press the **ESC** key to stop recording.
4. Click the **Stop Recording** button.



5. Name the recording and click **Save**.
6. Select **Produce your recording** or **Edit your recording** and click **OK**.



Import PowerPoint Slides

Import PowerPoint slides directly into Camtasia and quickly edit them to match audio narration.

Import PowerPoint Slides

Import .ppt or .pptx slides directly into Camtasia and record voice narration for the slides.

1. Select **File > Import Media**.
2. Select a PowerPoint presentation file (.ppt or .pptx).

Note: You can also drag a PowerPoint presentation file onto the Media Bin to import the slides.

3. Click **Open** (Windows) or **Import** (Mac).
4. On Mac, Microsoft PowerPoint opens.
 - o Click the **Grant Access** button.
 - o In the Slides dropdown, select **All**, **Range**, or **Single**.
 - o Click **Import**.
5. Camtasia imports the slides as images into the Media Bin. Drag the slides onto the timeline.
6. The default duration for each slide is 5 seconds. Drag the end of the clip to extend the duration. See [Change Default Slide Duration](#) to change the duration before importing slides and other media.
7. Record [voice narration \(https://www.techsmith.com/learn/?post_type=tutorial&p=182335\)](https://www.techsmith.com/learn/?post_type=tutorial&p=182335).

Tip: Create a Video Table of Contents.


Add markers to the timeline to create a video table of contents with the final video. See [Add Markers & Video Table of Contents \(https://www.techsmith.com/learn/?post_type=tutorial&p=182313\)](#).

Change the Default Slide Duration

The default duration of slides and images added to the timeline is 5 seconds.

1. Select **Edit** (Windows) or **Camtasia 2023** (Mac) > **Settings** (macOS 13 or later) or **Preferences** (Windows and macOS 12 or earlier).
2. Click the **Timing** (Windows) or **Timeline** (Mac) tab.

3. Enter a default duration for the **Images** (Windows) or **Default Image Duration** (Mac).



4. Click **OK** (Windows) or close the Preferences dialog (Mac) to save the changes.

Tip: Adjust the duration of a slide.

To adjust the duration of a single slide, select the desired clip on the timeline. Then drag the end of the clip in or out. You may need to insert space between slides before extending the duration (see below).

Insert Space Between Slides

Create space between slides to make room for longer narrations or to insert additional media.

Move Media on One Track:

Hold the **Shift** key and drag the media to a new location on the timeline. Media to the right of the clip moves with the selection.

Move Media on Multiple Tracks:

1. **Shift+click** to select the first clip on each track.
2. Hold the **Shift** key and drag the media to a new location on the timeline. Media to the right of the clip moves with the selection.

Note: For Mac, you must click and hold the mouse button on the last selected clip as you drag to move media to the right of the selection.

Record Voice Narration


Learn how to record a voice-over for video.

The Audio Narration option allows you to record a voice-over while playing back the video on the timeline. You can paste a script to read from during the recording.


Tip: Start with great audio.

- Use the best quality microphone you can afford.
- Use default Camtasia Recorder audio settings or start your project with [TechSmith Audiate](https://www.techsmith.com/audiate.html) (<https://www.techsmith.com/audiate.html>) to record and edit voice-overs.
- ALWAYS do a short test recording to ensure audio is being recorded.
- Use [Audio Effects](https://www.techsmith.com/learn/?post_type=tutorial&p=196578) (https://www.techsmith.com/learn/?post_type=tutorial&p=196578) to enhance or correct audio.
- Add audio points to adjust the volume of specific areas of the waveform.

1. Click the **Voice Narration** tab.



2. Select the desired audio device from the dropdown.
3. To test the audio level, speak as you would during the recording. Drag the slider to adjust the audio level if the meter's color does not change to green or changes to yellow or red.




4. Type or paste an optional script into the text box.
5. Select **Mute timeline during recording** (Windows) or **Mute speakers during recording** (Mac) to prevent audio on the timeline from playing through your speakers or headphones.
6. Drag the playhead to the position on the timeline to start recording audio.
7. Click the **Start Voice Recording** button.
8. Camtasia plays back the video on the timeline. Speak into a microphone to record your voice narration.
9. Click the **Stop** button to stop recording.
10. On Windows, enter a file name and click **Save**.


The audio clip is added to the timeline and Media Bin.

Edit Media on the Canvas

Learn how to control the appearance of media and add ruler guides to align media on the canvas.

Edit the appearance of media in a video with the following canvas actions:

Select Media	Click to select the media on the canvas. To select multiple media, Shift+click media on the canvas.
Move, Resize, or Rotate Media with canvas controls	<ul style="list-style-type: none">• Move media: Click and drag the media to a new location on the canvas.• Resize media: Drag a handle on the media in or out.• Rotate media: Drag the center handle on the media to rotate. <p>Note: To adjust the size of the Canvas controls such as the handles to resize and rotate on Windows only, select Edit menu > Preferences > Program tab. Select an option from the Canvas control size dropdown.</p> 
Show/Hide Canvas Ruler	Select View menu > Show/Hide Canvas Ruler to enable or disable the canvas ruler.
Open Media Properties	<ol style="list-style-type: none">1. Click to select the media on the canvas. To select multiple media, Shift+click media on the canvas.2. Click the Properties button to view the Properties panel (https://www.techsmith.com/learn/tutorials/camtasia/media-properties/).
Reorder Media	Right-click media and select Arrange .




The media updates on the timeline to reflect the new z-order.

Align Media

The following options are available to align media:

- **Canvas guides:** As you drag media on the canvas, canvas guides appear. Drag media on the canvas until it aligns with the edge, center, or other media guidelines.



To disable canvas snapping guidelines, select **View > Enable Canvas Snapping** to remove the checkmark.


- **Ruler guides:** See [Align Media with Ruler Guides](#).

Align Media with Ruler Guides


Create ruler guides to align media or create visual boundaries on the canvas.

To create ruler guides:

1. Select **View menu > Show Canvas Ruler**.
2. Click and drag the left canvas ruler onto the canvas to add a vertical ruler guide.



3. Click and drag the top canvas ruler onto the canvas to add a horizontal ruler guide.



4. Click and drag a ruler guide to adjust its position.

Tips:


- Change the canvas magnification to view your work with pixel-perfect accuracy. See [Explore the Canvas \(https://www.techsmith.com/learn/tutorials/camtasia/working-with-the-canvas/\)](https://www.techsmith.com/learn/tutorials/camtasia/working-with-the-canvas/).
- Disable canvas snapping to manually align media with ruler guides. Select **View menu > Enable Canvas Snapping** to remove the checkmark in the menu.
- To remove ruler guides from the canvas, **right-click** (Windows) or **Control+click** (Mac) on a ruler guide and select **Remove Ruler Guide** or **Remove All Ruler Guides**.

Explore the Timeline

Learn how to use the timeline to arrange your video.

Timeline Overview

The timeline displays the sequence of all media in a video. Use the timeline to assemble a video.



Add Content to a Video

Drag media from the [Media Bin](https://www.techsmith.com/learn/?post_type=tutorial&p=182296) (https://www.techsmith.com/learn/?post_type=tutorial&p=182296), [Camtasia Assets](https://www.techsmith.com/learn/tutorials/camtasia/camtasia-assets/) (<https://www.techsmith.com/learn/tutorials/camtasia/camtasia-assets/>), or [Library](https://www.techsmith.com/blog/?post_type=tutorial&p=182344) (https://www.techsmith.com/blog/?post_type=tutorial&p=182344) subtabs onto the timeline. As you make edits on the timeline, the Media Bin always maintains the original version of your media.


Preview a Video

The playhead location represents a point in time in the video. All media at that point on the timeline display as the current frame on the [canvas](https://www.techsmith.com/learn/?post_type=tutorial&p=182299) (https://www.techsmith.com/learn/?post_type=tutorial&p=182299).




Preview a Frame



Drag the playhead to the desired position on the timeline. Camtasia displays the frame on the canvas.

<p>Preview Video</p>	<p>Drag the playhead to the desired position on the timeline. Click the Play button to preview the video.</p>  <div style="border: 1px solid green; padding: 10px; margin-top: 10px;"> <p style="text-align: center;">Tip: Save time editing with variable speed shortcuts.</p> <ul style="list-style-type: none"> • Press J to reverse the timeline playback at normal (1x), 2x, 4x, or 8x speed. • Press K to pause the timeline playback. • Press L to play the timeline forward at normal (1x), 2x, 4x, or 8x speed. </div>
<p>Preview One Track (Solo Track) Preview one selected track on the canvas.</p>	<p>Hold Alt key (Windows) or Option key (Mac) and click the  icon to the left of the track. The icon changes to  and all other tracks are disabled.</p> <div style="border: 1px solid green; padding: 10px; margin-top: 10px;"> <p>Note: If you export the video with a solo track enabled, only the solo track is exported.</p> </div>
<p>Zoom the Timeline</p>	<p>Drag the zoom slider to zoom in on the timeline for more precise editing.</p>  <p>To view the project in full, click the  icon to fit the entire project to the timeline.</p>

Timeline Tracks

The timeline is organized into layers called tracks. Media on the top layers cover media on the layers below.




<p>Track Order</p> <p>For visual media on the timeline, the track order controls the z-order position for media in a video.</p>	<p>To reorder tracks, click near the track name and drag to a new position on the timeline.</p>
<p>Detach/Reattach Timeline</p> <p>Detach the timeline to view more tracks at one time or to move to another monitor for precise editing.</p>	<p>To detach the timeline: Select View > Timeline > Detach Timeline or press Ctrl+3 (Windows) or Command+3 (Mac).</p> <p>To reattach the timeline: Press Ctrl+3 (Windows) or Command+3 (Mac) to reattach the timeline.</p>
<p>Change the Track Size (Track Height)</p>	<p>To resize all tracks, drag the track slider.</p>  <p>To resize only one track, drag the border between tracks up or down.</p> 
<p>Add a Track</p> <p>Add an unlimited number of tracks to the timeline.</p>	<p>Complete any of the following to add a track:</p> <ul style="list-style-type: none"> • Click + to add a track to the timeline. • Drag and drop media from the Media Bin or Library tabs onto an empty area on the timeline. • Right-click a track and select Insert Track > Above or Below.
<p>Remove a Track</p>	<ul style="list-style-type: none"> • Right-click a track name and select Remove Track. • Right-click a track name and select Remove All Empty Tracks.

Scroll through Tracks

When several tracks are on the timeline, use the scroll bar on the right side of the timeline up or down to view more tracks.

Click and drag the scroll bar on the right side of the timeline up or down to view more tracks.



Rename a Track

Double-click the track name and type a new name.


Lock / Unlock Track

Lock a track to prevent editing or other changes to the media on the track.

Lock a Track

Click the  icon to the left of the track.

The icon turns white and the track dims with a lined effect to indicate the track is locked.



Unlock a Track

Click the white lock icon to the left of the track. The icon turns gray and the track brightens to indicate the track is unlocked.

About Locked Tracks

- Media on a locked track appears on the canvas, preview, and exported video.
- Media on a locked track cannot be cut, copied, deleted, pasted, or modified in any way.


Enable / Disable Track

Disable a track to remove media from the canvas, preview, and exported video.

Disable a Track

Click the  icon to the left of the track.

The icon turns white and the track dims to indicate the track is off.



Enable a Track

Click the white eye icon to the left of the track.

The icon turns gray and the track brightens to indicate the track is on.

About Turned Off Tracks

- Media on disabled tracks is not included in the exported video.
- Disable a track to sample various audio clips. For example, to hear only the background music track, turn off the voice-over track.
- Media on a disabled track cannot be cut, copied, deleted, pasted, etc.


Enable / Disable Magnetic Track

Automatically remove spaces between media on a track.

Enable Magnetic Track

Click the  icon to the left of the track.


Spaces between media are automatically removed.



Disable Magnetic Track

Click the  icon to the left of the track.

Spaces can be added between media on the track.



About Magnetic Tracks


- You can move or rearrange media on the track but cannot add space between media.
- Groups on magnetic tracks keep spaces between media.

To learn about common timeline editing tasks on magnetic tracks, see [Close Timeline Gaps with Magnetic Tracks \(https://www.techsmith.com/learn/?post_type=tutorial&p=182317\)](https://www.techsmith.com/learn/?post_type=tutorial&p=182317).

Show / Hide Quiz or Marker View

When a quiz or marker is added to the timeline, the quiz or marker view automatically opens.

Click  and select which tracks to turn on or off.



To learn more about quizzes and markers, see [Build Quizzes & Surveys \(https://www.techsmith.com/learn/?post_type=tutorial&p=182328\)](https://www.techsmith.com/learn/?post_type=tutorial&p=182328) or [Add Markers & Video Table of Contents \(https://www.techsmith.com/learn/?post_type=tutorial&p=182313\)](https://www.techsmith.com/learn/?post_type=tutorial&p=182313).

Tip: Speed up your workflow with efficient editing skills.


See [Editing In-Depth \(https://www.techsmith.com/learn/?post_type=tutorial&p=182314\)](https://www.techsmith.com/learn/?post_type=tutorial&p=182314) for techniques to edit video more efficiently and to avoid recording multiple times.

Add Markers & Video Table of Contents

Add markers to indicate points on the timeline or to create an interactive table of contents for navigation for your viewers.

Working with Markers

Markers indicate points on the timeline or within media.



Use markers to:

- Add interactive table of contents to your video to create navigation points for your viewers. See [Create a Video Table of Contents](#).
- Mark editing points such as mistakes during recording, sections to cut out, etc.
- Set points to split a long video into multiple videos.
- Automatically mark each slide on the timeline when recording a PowerPoint or Keynote presentation.

Option	Description
Add a marker while recording	Press Ctrl+M (Windows) or Shift+Ctrl+Option+Command+M (Mac) while recording.
Add a timeline marker	Timeline markers always maintain their original location on the timeline and are not impacted by timeline edits. <ol style="list-style-type: none">1. Drag the playhead to the desired location on the timeline.2. Press Shift+M.
Add a media marker	Media markers are attached to the media. If you move the media on the timeline, the marker moves with the media. <ol style="list-style-type: none">1. Press Ctrl+M to open the marker view.2. Click the plus icon on the media.



Show / hide marker view

When the Marker view is shown, Camtasia displays the Marker track and the marker names on the timeline. Show the Marker view to edit markers.



Press **Ctrl+M**.

Next marker

Ctrl+]

Previous marker

Ctrl+[

Timeline select to previous marker

Press **Ctrl+Shift+[** to make a timeline selection between the playhead and the previous marker.

Timeline select to next marker

Press **Ctrl+Shift+]** to make a timeline selection between the playhead and the next marker.

Change marker name

Note: If you include a [table of contents](#) when you export a video, the marker names appear as the table of contents entries within the video.


1. Click to select marker.
2. Enter new name in **Properties**.



3. Press **Enter**.


Turn a timeline marker into a media marker

1. Press **Ctrl+M** to show the marker view.
2. Hover over the media to display the  icon.
3. Click the  icon where the vertical marker line crosses the media.



Turn a media marker into a timeline marker

1. Press **Ctrl+M** to show the marker view.
2. Hover over the Marker track to display the  icon.
3. Click the  icon where the vertical marker line crosses the media.



Move the location of a marker

Click and drag the marker to the desired position.

Delete a marker


1. Click to select a marker.
2. Press **Delete**.

Delete all markers


Select **Modify > Markers > Remove all Markers**.

Create a Video Table of Contents

Add markers on the timeline as navigation points in your video table of contents. The marker names appear in the table of contents in the video.



1. To show the Marker track, click the **Quiz/Marker** dropdown and select Marker or press **Ctrl+M**.



2. Drag the playhead to the desired location on the timeline. To add a marker, click the Marker track or press **Shift+M** to add a timeline marker.
3. Enter a name in the Properties panel and press **Enter**.

Export Video with Table of Contents

Note: The TechSmith Smart Player is required for table of contents, closed captions, search, quizzing, and hotspots in a video. To include the TechSmith Smart Player, export the video to Local File or Screencast.

Windows

Export to one of the following locations:

- **Screencast:** Select **Export > Screencast**.
- **Local File:** See below for your version.

Local File – Camtasia Version 2022 and Later

▼ View details

1. Select **Export > Local File**.
2. In the Export Local File dialog, select the **MP4 with Smart Player** option from the File type menu.
3. Click **Next**.

Mac

Export video to one of the following locations:

- **Screencast:** Select **Export > Screencast**.
- **Local File:**
 1. Select **Export > Local File > Export to MP4 (.mp4)**.
 2. Select the following options:
 - File format: Export to MP4 (.mp4)
 - Enable **Export as Web Page** option.
 - Enable **Create table of contents from markers** option.
 3. Click **Export**.

To view the video table of contents, viewers must click the **Table of Contents** button on the video controller.



Freeze Video Clips with Extend Frame

Learn how to extend a frame to lengthen the duration of a video clip.

Lengthen a video clip to match the audio or voice narration, or for more time to explain a particular screen or moment in your recording.


Windows:

1. Drag the playhead to the frame to extend.
2. Right-click the video clip and select **Extend Frame** or press **Shift+E** on the keyboard.
3. The Extend Frame dialog appears. Enter the desired duration of the extended frame.
4. Click **OK**.

You can also extend the frame by holding the **Alt** key while dragging the end of a clip.

Mac:

Hold the **Option** key while dragging the end of the clip.



Ripple Extend

Move other media to the right on the same track to make room for the longer clip.

Windows:

Press and hold **Shift+Alt** while dragging the end of the media.

Mac:

1. Press and hold the **Option** key while completing the following steps.
2. Click and hold the end of the clip to extend. The Extend Frame icon appears.



3. Press and hold the **Command** key while dragging the end of the clip.

Add Exported Frame as Image

Add a frame to a new track on the timeline for more flexible editing.

1. Drag the playhead to the desired frame.
2. Right-click (Windows) or Ctrl+click (Mac) the playhead and select **Add Exported Frame**.

Camtasia exports the frame as an image to your Media Bin and automatically adds it to a new track on the

Join Clips Together

Learn to stitch clips back together to select, move, and edit them as one.

Stitch Media

If you split media to break it apart, stitch the clips back together to edit them as one.

To learn more about splitting, see [Remove Mistakes \(Trim & Split\)](https://www.techsmith.com/learn/?post_type=tutorial&p=182315) (https://www.techsmith.com/learn/?post_type=tutorial&p=182315).

1. Click and drag your cursor to select the two media clips you want to stitch together.
2. Right-click (Windows) or Ctrl+click (Mac) the media and select **Stitch Selected Media**.

- Only sections of media created from the original clip can be stitched together.
- Media must be next to each other to be stitched.
- Media is automatically stitched back together when cut.
- Media is NOT stitched and a gap appears on the timeline when deleted.

Unstitch Media

To separate media:

- **Windows:** Right-click the stitch and select **Unstitch**.
- **Mac:** Ctrl+click the stitch and select **Unstitch Media**.

Add an Enhancement to Stitched Media

Stitched media share the same properties. Any animations or effects that you add to stitched media applies to both clips. Animations can span the stitch.

1. Stitch the clips together. See [Stitch Media](#).
2. Click an enhancement tab such as **Animations**, **Audio Effects** or **Visual Effects**.
3. Drag the enhancement to the stitched media on the timeline.
4. (Optional) If applying an animation, adjust the length of the animation arrow to span the stitch.

Move Multiple Clips at Once

Learn how to move clips across tracks to create space or to move a group of media.

Move Media on One Track

Hold the **Shift** key and drag the media to a new location on the timeline. Everything to the right of the clip moves with the selection.

Move Media on Multiple Tracks

1. **Shift+click** to select the first clip on each track.
2. Hold the **Shift** key and drag the media to a new location on the timeline. Everything to the right of the clip moves with the selection.

Ripple Move & Extend Frame

Learn how to improve your editing skills and take your videos to the next level with ripple move and extend frame.

Sometimes you need to create space in the middle of a project to make room for a longer explanation or to add additional content.


Ripple move or ripple split media to create the space, then extend a video frame to accommodate longer audio recording.

Rearrange Media or Insert Space

Option	Steps
Insert Space at a Specific Point (Ripple Split)	Hold the Shift key and drag the playhead. Camtasia splits the media across all tracks and moves everything to the right of the playhead.
Move Media to Insert Space (Ripple Move)	<p>Move Media on One Track:</p> <p>Hold the Shift key and drag the media to a new location on the timeline. Everything to the right of the clip moves with the selection.</p> <p>Move Media on Multiple Tracks:</p> <ol style="list-style-type: none">1. Shift+click to select the first clip on each track.2. Hold the Shift key and drag the media to a new location on the timeline. Everything to the right of the clip moves with the selection.

Extend Frame (Freeze Frame)

Extend a frame to lengthen the duration of a video clip to match the audio or voice narration. You can also add a video frame as an image on your timeline for more flexible editing, or save it as an image file for use outside of your project.

Option	Steps
<p>Extend the Frame of a Video Clip</p> 	<p>Windows:</p> <ol style="list-style-type: none"> 1. Drag the playhead to the frame to extend. 2. Right-click the video clip and select Extend Frame or press Shift+E on the keyboard. 3. The Extend Frame dialog appears. Enter the desired duration of the extended frame. 4. Click OK. <p>You can also extend the frame by holding the Alt key while dragging the end of a clip.</p> <p>Mac: Hold the Option key while dragging the end of the clip.</p>
<p>Move Other Media While Extending the Frame (Ripple Extend)</p>	<p>Move other media to the right on the same track to make room for the longer clip.</p> <p>Windows: Press and hold Shift+Alt while dragging the end of the media.</p> <p>Mac:</p>

Option	Steps
	<ol style="list-style-type: none"> 1. Press and hold the Option key while completing the following steps. 2. Click and hold the end of the clip to extend. The Extend Frame icon appears.  3. Press and hold the Command key while dragging the end of the clip.
Add Exported Frame as Image	<ol style="list-style-type: none"> 1. Drag the playhead to the frame to export. 2. Right-click the playhead and select Add Exported Frame. Camtasia adds the frame to the timeline.
Save Video Frame as Image	<p>Save the current frame (on the canvas) as an image file (BMP, GIF, JPG, or PNG).</p> <ol style="list-style-type: none"> 1. Drag the playhead to

Option	Steps
	<p>the frame to export.</p> <ol style="list-style-type: none"><li data-bbox="1279 237 1468 342">2. Select Export > Export frame as.<li data-bbox="1279 367 1438 667">3. The Export Frame As dialog appears. Enter a file name and select a file location.<li data-bbox="1279 693 1458 1035">4. Select a file format from the Save as type field (Windows) or type a file format after the filename (Mac).<li data-bbox="1279 1060 1435 1081">5. Click Save.

Close Timeline Gaps with Magnetic Tracks

Learn how to automatically remove the space between media on a track to insert or rearrange media on the timeline.


Magnetic tracks automatically remove all space between media on a track.

- You can move or rearrange media on a magnetic track but cannot add space between media.
- Groups on magnetic tracks keep spaces between media.

Enable Magnetic Track

Click the  icon to the left of the track.

Spaces between media are automatically removed.



Insert Media

Drag media from the **Media Bin** or **Library** onto a track.

If you add media between two clips, other media on the track automatically shifts to insert space.

Rearrange Media


Click and drag media to a new location on the track.

If you move media between two clips, the other media on the track automatically shifts to insert space.

Disable Magnetic Track

Click the  icon to the left of the track.

Spaces can be added between media on the track.




How to Use Group Tabs

Learn how to group media to organize your timeline and edit multiple pieces of media at once.

Working with Groups

A group is a set of media, annotations, and/or enhancements combined into a single track.



Group media to:

- Organize the timeline.
- Move a set of media on the canvas or timeline.
- Edit properties such as scale or opacity for all media in the group together.
- [Create custom assets](https://www.techsmith.com/learn/tutorials/camtasia/create-custom-assets/) (<https://www.techsmith.com/learn/tutorials/camtasia/create-custom-assets/>) that can be shared and reused across projects.
- [Save a media group to your library](#) to use in a future project.

Characteristics of a group:


- Groups can contain an unlimited number of media, annotations, enhancements, or tracks.
- Groups can be nested in other groups for further organization.
- Spaces are maintained between media in groups on magnetic tracks.





Create a Group




1. Hold **Shift+click** to select media on the timeline to add to the group.
2. Right-click (Windows) or Control+click (Mac) the selection and select **Group**, or press **Ctrl+G** (Windows) or **Command+G** (Mac).




Edit a Group


Some groups in the default Camtasia library and on the [TechSmith Assets for Camtasia website](https://library.techsmith.com/camtasia) (<https://library.techsmith.com/camtasia>) have editable properties such as title, subtitle, or shapes. See [Discover the Properties Panel](https://www.techsmith.com/learn/tutorials/camtasia/media-properties/) (<https://www.techsmith.com/learn/tutorials/camtasia/media-properties/>).

Option	Steps
<p>Open Group Expand a group on the timeline to view and edit media individually.</p>	<p>Click the + icon on the group on the timeline or click a group on the canvas and press Ctrl+Shift+G (Windows).</p>  <p>Media within the group appear on separate tracks. The group name displays in a tab</p>

Option	Steps
	<p>above the timeline.</p> 
<p>Close Group Collapse items within a group to a single track.</p>	<p>Click the  icon on the group tab above the timeline or press Control+Shift+U (Windows).</p>  <p>The group displays on a single track on the timeline.</p>
<p>Navigate Between Groups and Timeline</p>	<p>Click a tab to navigate between open groups or the main timeline. Camtasia displays a green tab name for the currently selected tab.</p> 
<p>Add Media to an Existing Group</p>	<ol style="list-style-type: none"> Right-click (Windows) or Control+click (Mac) media on timeline or canvas and select Cut. Click the  icon to open the target group.  Paste media into the group: <ul style="list-style-type: none"> On Windows, right-click the canvas or an empty section of the timeline and select Paste. On Mac, click the Add a Track icon. Control+click the empty track and select Paste Media at Playhead. 
<p>Remove Media from Group</p>	<ol style="list-style-type: none"> Right-click (Windows) or Control+click (Mac) clip on timeline and select Cut. Click the  icon to close the tab. Paste media:

Option	Steps
	<ul style="list-style-type: none"> On Windows, right-click the canvas or an empty section of the timeline and select Paste. On Mac, click the Add a Track icon. Control+click the empty track and select Paste Media at Playhead. 
Rename Group	Double-click group tab on timeline and type new group name.
Ungroup Media	Right-click (Windows) or Control+click (Mac) group on the timeline and select Ungroup .
Edit Group Properties	<p>Select a group on the timeline or canvas and click the Properties button.</p>  <p>The Properties panel displays a list of editable group properties (also known as Quick Properties). See Create Custom Assets (https://www.techsmith.com/learn/tutorials/camtasia/create-custom-assets/).</p>
Resize All Media in a Group	<p>Select a group on the timeline or canvas and drag the corner handles on the canvas. All media in the group is scaled proportionately.</p> 
<p>Resize Group Area</p> <p>Set the overall area of the group to a different size for advanced editing workflows. The size of individual media within the group is not affected.</p>	<p>Right-click (Windows) or Control+click (Mac) a group on the timeline and select Resize Group. Select one of the following options:</p> <ul style="list-style-type: none"> Canvas Size: The group is the same size as the canvas. Camtasia crops any items that extend beyond the canvas edge. This option is useful to center a group on the canvas and prevent it from being moved accidentally.  <ul style="list-style-type: none"> Visible Size: The group area includes all items without cropping. This is useful to zoom out on items that extend beyond the canvas. 

Option	Steps
	<ul style="list-style-type: none"> • Custom Size: Enter a custom height and width in pixels and click Resize. This is useful to restrict media from displaying beyond an area of specific size. 
<p>Crop Group on the Canvas</p>	<ol style="list-style-type: none"> 1. Click to select a group on the timeline or canvas. 2. Click the Crop button.  <ol style="list-style-type: none"> 3. Drag the handles on the canvas to the desired size. 
<p>Move Group</p>	<p>Click and drag to move a group:</p> <ul style="list-style-type: none"> • On the timeline to a different time in the video. • On the canvas to a different location on the screen in the video.
<p>Add Enhancements Add animations, behaviors, and effects (https://www.techsmith.com/learn/tutorials/camtasia/enhance-video/) to media groups or individual media in groups.</p>	<p>To a Group: Click and drag enhancements onto a group on the timeline.</p> <p>To Individual Media:</p> <ol style="list-style-type: none"> 1. Click the + icon to open the group.  <ol style="list-style-type: none"> 2. Click and drag enhancements onto media in the group on the timeline.

Option	Steps
<p>Rotate Group on the Canvas</p>	<p>Select a group on the timeline or canvas and drag the center handle.</p> 

Add a Group to the Library


Save media groups to your Library to share or reuse in projects.

1. Right-click (Windows) or Control+click (Mac) a group on the timeline and select **Add to Library**.
2. Enter a name.
3. Select a library.
4. Click **Use Canvas Size** or **Use Visible Size** to set the saved group dimensions. To learn more about these options, see [Reuse Media Across Projects \(Asset Libraries\)](https://www.techsmith.com/learn/tutorials/camtasia/library/) (<https://www.techsmith.com/learn/tutorials/camtasia/library/>).
5. Click **OK** (Windows) or **Add** (Mac).


Preview a Group

Preview only the media within a group on the canvas.

1. Click the **+** icon to open a group.




2. Click the **Preview Mode** button.



- **Enable Preview Mode:** All media on the timeline is visible on the canvas.



- **Disable Preview Mode:** Only the group is visible on the canvas. The exported video includes all media.






Remove Mistakes (Trim & Split)

Learn how to remove mistakes when screen recordings don't go as planned, and how to split media into multiple clips.

Remove Unwanted Parts

Camtasia offers multiple options to remove unwanted parts of media.

Option	Steps
<p>Trim (Mark-in or Mark-out a Clip)</p> 	<p>Reduce or extend the start or end of a clip without cuts or splits.</p> <ol style="list-style-type: none">1. Click to select a clip on the timeline (Mac only).2. Hover the cursor over the beginning or end of the clip.3. Drag the end of the clip in or out. 
<p>Cut</p>	<p>A cut removes a selection from the timeline and adds it to the clipboard. You can cut a single clip or cut across multiple clips.</p> <p>To Cut Media:</p> <p>Click to select media on the timeline and click the  button. Hold Shift+click to select multiple media.</p> <p>To Cut a Timeline Selection:</p> <ol style="list-style-type: none">1. Click the  button to lock tracks on timeline that contain media you do not want to cut.2. Click and drag the green or red handles on the playhead to make a selection. For a precise selection, drag the Zoom slider to zoom in on the timeline content.  <ol style="list-style-type: none">3. Click the  button. The selection is removed and the remaining media is stitched together.4. To paste the selection on the timeline, move the playhead to a new location and click the  button.

Option	Steps
<p>Delete Media or Selection</p>	<p>button.</p> <p>To Delete Media: Select media on the timeline and press Delete.</p> <p>To Delete a Timeline Selection:</p> <ol style="list-style-type: none"> 1. Click the  button to lock tracks on timeline that contain media you do not want to delete. 2. Click and drag the green or red playhead handles to make a selection. For a precise selection, drag the Zoom slider to zoom in on the timeline content.  <ol style="list-style-type: none"> 3. Press Delete on the keyboard.

Rearrange Media or Insert Space

Split media into multiple clips to:

- Move and edit each clip separately.
- Insert transitions, title slides, or graphics between clips.

Option	Steps
<p>Split</p> 	<ol style="list-style-type: none"> 1. Drag the playhead to the location to split. 2. Click the  button or press S on the keyboard. <p>All media on the timeline splits into separate clips.</p> <p>To split selected media, click to select media before splitting. Hold Shift+click to select multiple media.</p>
<p>Insert Space at a Specific Point (Ripple Split)</p>	<p>Hold the Shift key and drag the playhead. Camtasia splits the media across all tracks and moves everything to the right of the playhead.</p>

Editing In-Depth


Learn editing techniques to minimize recording again and edit video more efficiently.

Make a Selection

Select media to edit, move, or delete on the timeline.

Select Part of the Timeline


Click and drag the green or red playhead handles to make a selection. The selected area is highlighted in blue.



For a precise selection, drag the **Zoom** slider to zoom in or out on the timeline.




Select Media on the Timeline




Click to select media. **Shift+click** to select multiple media. The selected media is outlined in yellow.

To select all media in an area on the timeline, click and drag the cursor across the media.



Rearrange Media or Insert Space


Magnetic Track



Automatically remove all space between media on a track to insert or rearrange media on the timeline.

Enable Magnetic Track

Click the  icon to the left of the track. Any space between media is automatically removed.



Insert Media


Drag media from the [Media Bin](https://www.techsmith.com/learn/tutorials/camtasia/import-manage-media/) or [Library](https://www.techsmith.com/learn/tutorials/camtasia/library/) onto a track. If you add media between two clips, other media on the track automatically shifts to insert space.

Rearrange Media


Click and drag media to a new location on the track. If you move media between two clips, the other media on the track automatically shifts to insert space.

Disable Magnetic Track

Click the  icon to the left of the track. Spaces can be added between media on the track.



Split



Split media into multiple clips to:

- Move and edit each clip separately.
- Insert transitions, title slides, or graphics between clips.

To Split Media:

1. Drag the playhead to the location to split.
2. Click to select media to split. **Shift+click** to select multiple media.
3. Click the  button or press **S** (Windows) or **Command+T** (Mac) on the keyboard.

To split all media on the timeline, press **Control+Shift+S** (Windows) or **Command+Shift+T** (Mac) on the keyboard.

Insert Space at a Specific Point (Ripple Split)



Hold the **Shift** key and drag the playhead. Camtasia splits the media across all tracks and moves everything to the right of the playhead.

Move Media to Insert Space (Ripple Move)

Move Media on One Track:

Hold the **Shift** key and drag the media to a new location on the timeline. Everything to the right of the clip moves with the selection.


Move Media on Multiple Tracks:

1. **Shift+click** to select the first clip on each track.
2. Hold the **Shift** key and drag the media to a new location on the timeline. Everything to the right of the clip moves with the selection.

See [Ripple Move & Extend Frame](https://www.techsmith.com/learn/tutorials/camtasia/ripple-move-and-extend-frame/) (<https://www.techsmith.com/learn/tutorials/camtasia/ripple-move-and-extend-frame/>) or [Move Multiple Clips at Once](https://www.techsmith.com/learn/tutorials/camtasia/ripple-move/) (<https://www.techsmith.com/learn/tutorials/camtasia/ripple-move/>).


Remove Unwanted Parts

Trim (Mark-in or Mark-out a Clip)



Reduce or extend the start or end of a clip without cuts or splits.

1. Click to select a clip on the timeline (Mac only).
2. Hover the cursor over the beginning or end of the clip.
3. Drag the end of the clip in or out.



Cut


A cut removes a selection from the timeline and adds it to the clipboard. You can cut a single clip or across multiple clips.

To Cut Media:

1. Click to select media or **Shift+click** to select multiple media on the timeline.
2. Click the  button.

To Cut a Timeline Selection:

1. Click the  button to lock tracks on timeline that contain media you do not want to cut.
2. Click and drag the green or red handles on the playhead to make a selection. For a precise selection, drag the **Zoom** slider to zoom in on the timeline content.



3. Click the  button. The selection is removed and the remaining media is stitched together.
4. To paste the selection on the timeline, move the playhead to a new location and click the  button.


Delete Media or Selection

To Delete Media:

Select media on the timeline and press **Delete**.

To Delete a Timeline Selection:


1. Click the  button to lock tracks on timeline that contain media you do not want to delete.
2. Click and drag the green or red playhead handles to make a selection. For a precise selection, drag the **Zoom** slider to zoom in on the timeline content.



3. Press **Delete** on the keyboard.

Extend Media (Freeze Frame)

Extend the Frame of a Video Clip



Extend a frame to lengthen the duration of a video clip to match the audio or voice narration.

Windows:

1. Drag the playhead to the frame to extend.
2. Click to select the clip on the timeline.
3. Right-click the clip and select **Extend Frame** or press **Shift+E** on the keyboard.
4. The Extend Frame dialog appears. Enter the desired duration of the extended frame.
5. Click **OK**.

	<p>You can also extend the frame by holding the Alt key while dragging the end of the clip.</p> <p>Mac: Hold the Option key while dragging the end of the clip.</p>
Add Exported Frame as Image	<p>Add a frame to a new track on the timeline for more flexible editing.</p> <ol style="list-style-type: none">1. Drag the playhead to the desired frame.2. Right-click (Windows) or Control+click (Mac) the playhead and select Add Exported Frame. <p>Camtasia exports the frame as an image to your Media Bin (https://www.techsmith.com/learn/tutorials/camtasia/import-manage-media/) and automatically adds the frame to a new track on the timeline.</p>
Save Video Frame as Image	<p>Save the current frame (on the canvas) as an image file (BMP, GIF, JPG, or PNG).</p> <ol style="list-style-type: none">1. Drag the playhead until the desired frame is displayed on the canvas.2. Select Export > Export frame as.3. The Export Frame As dialog appears. Enter a file name and select a file location.4. Select a file format from the Save as type field.5. Click Save.


Other Editing Tasks

Stitch Media

- Only sections of media created from the original clip can be stitched together.
- Media must be next to each other to be stitched.
- Media is automatically stitched back together when cut.
- Media is NOT stitched and a gap appears on the timeline when deleted.

To Stitch Media Together:

Right-click (Windows) or Control+click (Mac) the location where the two media clips touch and select **Stitch Media**.



To separate media, right-click on the stitch and select **Unstitch** (Windows) or **Unstitch Media** (Mac).

Placeholders

Convert to Placeholder: Replace media on timeline with a placeholder.


1. Click to select media on the timeline.
2. Right-click (Windows) or Control+click (Mac) the media and select **Convert to Placeholder**.
3. Edit the placeholder title and optional note in the properties.

Add Placeholder: Add a media placeholder to create a template or to replace content at a later time.

1. Drag the playhead to the desired location on the timeline.
2. Right-click (Windows) or Control+click (Mac) on the timeline and select **Add Placeholder**.
3. Edit the placeholder title and optional note in the properties.


See [Build a Video Template to Share](https://www.techsmith.com/learn/tutorials/camtasia/create-a-template/) (<https://www.techsmith.com/learn/tutorials/camtasia/create-a-template/>).

Replace Media on the Timeline



Quickly replace media on the timeline, while preserving properties, transitions, effects, audio points, and animations.

1. To switch media or placeholders on the timeline, drag new media from the [Media Bin](https://www.techsmith.com/learn/tutorials/camtasia/import-manage-media/) (<https://www.techsmith.com/learn/tutorials/camtasia/import-manage-media/>) or [Library](https://www.techsmith.com/learn/tutorials/camtasia/library/) (<https://www.techsmith.com/learn/tutorials/camtasia/library/>) onto the media or placeholder on the timeline. When a green outline appears around the media or placeholder, release your mouse button.




2. A menu appears with the replacement options. If the new media is a different duration than the original media or placeholder, select one of the following options:
 - o **Ripple Replace:** Shift all clips on the track to the right to insert space for the entire duration of the new media.
 - o **Replace From Start:** Trim the new media to fit the duration of the original media. If the new media is longer, the end of the clip is trimmed to fit the duration.
 - o **Replace From End:** Trim the new media to fit the duration of the original media. If the new media is longer, the beginning of the clip is trimmed to fit the duration.
 - o **Replace with Clip Speed:** Increase the playback speed of the new media to fit the duration of the original media.

Speed Up Editing with Audiate

Edit Camtasia media in Audiate to quickly find mistakes, improve audio, and edit like a pro with text-based editing.

Audiate + Camtasia


Text-based video editing with Audiate + Camtasia helps you edit video faster and easier than ever before.




Start with a recording or project in Camtasia Editor, then send video and audio over to Audiate. Quickly find mistakes and edit like a pro with text-based editing. Clean up any audio issues with professional-sounding audio effects. Then sync everything back to your Camtasia project automatically.

Edit Audio on the Camtasia Timeline in Audiate

1. Click to select an audio clip on the timeline in Camtasia Editor.



2. Select **Properties > Audio tab > Edit in Audiate** button, or right-click (Windows) or control+click (Mac) the audio clip on the timeline and select **Edit in Audiate**.



If you have not saved your Camtasia project, Camtasia prompts you to do so.

3. Audiate opens and transcribes the audio from Camtasia Editor.
4. In Audiate, complete your desired audio edits. See [Recommended Audio Edits](#).
5. Click the **Sync** button or select **File > Save and Sync**.



Audiate automatically syncs your edits to the linked media on the Camtasia timeline.

Recommended Audio Edits


Try these editing recommendations to speed up the editing process and improve the quality of your video.



Hesitations and Pauses

Audiate automatically recognizes hesitations, such as “Umms” or “Ahhs” and pauses in speech.


Click the **Suggested Edits** dropdown in the upper-left corner to automatically apply the recommended edits to these hesitations and pauses.



Text-Based Audio Edits

Audiate transcribes your narration into plain text, making any issues easy to spot and remove. Delete words or mistakes, or silence hesitations. Your audio and video edits are automatically synced to your Camtasia timeline.

See [Edit Audio and Mistakes \(https://www.techsmith.com/learn/?post_type=tutorial&p=195833\)](https://www.techsmith.com/learn/?post_type=tutorial&p=195833).



Generate Audio from Text or a Script

Is your recording environment a little noisy, or do you prefer not to use your own voice?

Replace your voice-over with a variety of customizable AI voices in different languages, styles, and tones.

See [Generate Audio from Text or a Script](https://www.techsmith.com/learn/?post_type=tutorial&p=240596) (https://www.techsmith.com/learn/?post_type=tutorial&p=240596).



Apply Audio Effects

Use studio-quality effects to easily remove room noise, enhance your voice, and solve common audio issues.

See [Improve Audio with Effects](https://www.techsmith.com/learn/?post_type=tutorial&p=138562) (https://www.techsmith.com/learn/?post_type=tutorial&p=138562).



Generate Captions

Save time and automatically generate captions based on the audio transcription or a script.

See [Sync Options in Audiate](#).



Precise Edits

Click the **Waveform Editor** button



or

press **Ctrl+1** (Windows) or **Command+1** (Mac) to show the audio waveform for precise audio editing.

See [Edit Audio and Mistakes](https://www.techsmith.com/learn/?post_type=tutorial&p=195833) (https://www.techsmith.com/learn/?post_type=tutorial&p=195833).

Sync Options in Audiate

You can manage the sync options between your Camtasia and Audiate projects. To access these options in Audiate, click the **Sync** dropdown.






Option	Description
Edit Camtasia Timeline	Audiate syncs any edits made across all tracks on the Camtasia timeline for the duration of the linked media. This option keeps your video and audio in sync.
Edit Media Only	Audiate only syncs any edits made to the linked media in Camtasia. This option could cause media on your timeline such as video and audio to be out of sync.

Captions

Select your desired caption option from the **Captions** dropdown:

- **No Captions**
- **Default Captions:** Automatically generate a SRT caption file based on the audio transcription in Audiate to include with your linked media in Camtasia Editor.



Option	Description
	<ul style="list-style-type: none"> Dynamic Captions (Beta): Automatically generate a caption file based on the audio transcription in Audiate. Dynamic captions are burned into the video.  <p>In Camtasia, click to select the caption on the canvas and edit the properties to customize the dynamic caption font and style.</p> 
Unlink from Camtasia	Click Unlink From Camtasia to unlink the Audiate project from your media in Camtasia Editor. Audiate will no longer sync any edits made in Audiate with the media in Camtasia Editor.

Set the Tone with Background Music

Learn how to add background music from Camtasia Assets or another audio file to set the tone for your video.

Overview


Background music can help set the perfect tone for your video and make viewing more engaging and enjoyable for your audience. The right music can make your video feel:

- Lighthearted and playful
- Adventurous or intense
- Intriguing or curious
- Suspenseful
- And so much more!

Add Music from Camtasia Assets

Explore and select from hundreds of royalty-free instrumental and vocal audio tracks in various moods, styles, and genres directly in Camtasia.


1. To access free and premium assets in Camtasia version 2023.3.0 and later, select **Media tab > Camtasia Assets subtab**.




Note: To learn how to download assets in Camtasia version 2023.2.0 and earlier, see [Find Camtasia Assets on the Website \(http://techsmith.com/learn/tutorials/camtasia/install-assets/\)](http://techsmith.com/learn/tutorials/camtasia/install-assets/) tutorial.

2. Complete any of the following:


- In the Music category, click the ◀ and ▶ buttons to browse the assets. Or click **See All** to view additional assets.




- o Enter a search term into the **Search** field and press the **Enter** key.




- o Click the **Search Filter** dropdown to filter the results by free assets, safe search, or your recent searches.



3. Double-click to preview an asset.
4. Place the playhead on the timeline where you want the music to begin.
5. Drag the asset from the **Camtasia Assets** subtab onto the desired track on the timeline at the playhead.



6. Drag the end of the music clip in to remove any extra content.




To learn more about editing audio on the timeline, see [Edit Audio \(https://www.techsmith.com/learn/tutorials/camtasia/editing-audio/\)](https://www.techsmith.com/learn/tutorials/camtasia/editing-audio/).


Import an Audio File

To import your own audio files (MP3, M4A, WAV, and WMA) from your computer to use as background music:

1. Select the **Media tab > Media Bin** subtab.
2. Click **+** > **Import Media** or double-click in the Media Bin.
3. Click to select the media to import. **Control+click** (Windows) or **Command+click** (Mac) to select multiple files.
4. Click **Open** (Windows) or **Import** (Mac). The imported media appears in the Media Bin.
5. Place the playhead on the timeline where you want the music to begin.
6. Drag the media from the Media Bin onto the desired track on the timeline at the playhead.



7. Drag the end of the music clip in to remove any extra content.




To learn more about editing audio on the timeline, see [Edit Audio \(https://www.techsmith.com/learn/tutorials/camtasia/editing-audio/\)](https://www.techsmith.com/learn/tutorials/camtasia/editing-audio/).

Reduce Background Music During Narration

Ensure your background music doesn't drown out or distract from the voice narration in your video. Apply the Emphasize audio effect to voice narration clips to automatically decrease the volume of all other audio tracks.


To apply the Emphasize effect:

1. Click the **Audio Effects** tab.
2. Drag the **Emphasize** effect onto any clip on the timeline that includes your narration or microphone recording.



Note: Your microphone recording may be combined on a track with your camera recording.

3. Click **Properties** and select the **Audio Properties** subtab.



4. In the Emphasize properties, drag the **Emphasis** slider to change the volume for all other audio tracks on the timeline. **100%** mutes the audio of the other tracks for the duration of the applied clip.
5. Select **Ramp Position** to set where the volume transition starts and ends:

- o **Outside:** Complete audio change before and after the applied media plays.



- o **Span:** Change audio over the start and end of the applied media.



- o **Inside:** Begin audio change at the start of the applied media and before the end of the applied media.




6. Enter an amount in seconds to set the duration the **Ramp In** and **Ramp Out** volume transition occurs.

To learn more about Audio Effects, see [Add Audio Effects](https://www.techsmith.com/learn/tutorials/camtasia/add-audio-effects/) (<https://www.techsmith.com/learn/tutorials/camtasia/add-audio-effects/>).

4 Ways to Visualize Your Audio

Learn how to apply audio visualizers to animate audio clips in your video.

Visualize your voice narration, music clips, sound effects, or any audio to transform a static video into dynamic onscreen audio animations.



Here are four examples of audio content you can add audio visualizers to to help transform your video content.

Speaker Audio

Add an audio visualizer to help viewers connect with the speaker in an interview, customer quote or demo.

Add an avatar, picture, or webcam video of the speaker to provide context. If the speaker does not feel comfortable having their face appear in the video, you can include an icon of a phone or microphone.

Podcast Intro or Teaser

Use audio visualizers to create a trailer for your podcast episode. You can include an avatar or image to introduce the guest in the episode.

Video Intro or Outro

Combine a short audio visualizer and a sound effect to introduce and brand videos in a series or for your site.

Music Track

Start with your own or download music from [Camtasia Assets](https://www.techsmith.com/learn/tutorials/camtasia/camtasia-assets/) (<https://www.techsmith.com/learn/tutorials/camtasia/camtasia-assets/>). Audio visualizers combined with dynamic backgrounds can instantly bring music to life or set a particular mood.


For example, try this technique if you are creating an instructional video where you ask the viewer to complete an activity or brainstorm. The inspiring music and visuals can help fuel creativity or compliment webinar start music as you wait for participants to join.

See [Add a Dynamic Background](https://www.techsmith.com/learn/tutorials/camtasia/dynamic-backgrounds/) (<https://www.techsmith.com/learn/tutorials/camtasia/dynamic-backgrounds/>).


Add an Audio Visualizer

Note: Video elements with flickers or flashes, such as audio visualizers, may pose risks to some viewers. To learn more about creating accessible content, see this [support article](https://support.techsmith.com/hc/en-us/articles/20030747199117) (<https://support.techsmith.com/hc/en-us/articles/20030747199117>).


1. Drag an audio clip from the **Media** tab onto the timeline.
2. To find an audio visualizer:
 - **Camtasia 2023.3.0 and later:** Select **Media tab > Camtasia Assets subtab > Audio Visualizers > See All**. Browse or search for an audio visualizer.




- **Camtasia 2023.2.0 and earlier:** Click the **Library** tab and select the **Library dropdown > Camtasia 2023 Library > Audio Visualizers folder**.



3. Drag an audio visualizer onto a timeline track above the audio clip. Audio visualizers animate with audio.
4. Drag an end in or out to adjust the duration the audio visualizer appears in the video.



5. Click and drag to position the audio visualizer on the canvas.




6. Click the **Properties** button and adjust the settings to customize the audio visualizer.




Add an Avatar, Webcam, or Icon

You can add an avatar, profile picture, or webcam video of the speaker to provide context for the audio. If the speaker does not feel comfortable having their face appear in the video, you can include an icon of a phone or microphone.


1. On the **Annotations** tab, select the **Shapes** subtab and drag a shape annotation onto the canvas over audio visualizer.




2. Click and drag to position the annotation on the canvas. Hold the **Shift** key while dragging a handle to maintain a perfect circle or square.



3. On the **Visual Effects** tab, drag the **Media Matte** effect onto the shape annotation on the timeline.
4. Drag an image, avatar, or icon from the **Media** tab onto the timeline track below the shape annotation.
5. Click and drag to position the image on the canvas.



6. On the timeline, drag the ends of the shape annotation and the image in or out to set the duration to match the length of the audio visualizer.



Edit Audio

Learn how to edit audio on the timeline in Camtasia or send audio to Audiate for text-based editing.



Audio quality is just as important as video quality, if not more so.



- We detect audio errors more easily than visual errors.
- Most people won't watch a video with bad audio, even if the video itself is very good.
- People are more likely to continue watching a poor quality video if the audio is good.


Tip: Start with great audio.

- Use the best quality microphone you can afford.
- Use default Camtasia Recorder audio settings.
- ALWAYS do a short test recording to ensure audio is being recorded.
- Use [Audio Effects \(https://www.techsmith.com/learn/?post_type=tutorial&p=196578\)](https://www.techsmith.com/learn/?post_type=tutorial&p=196578) to enhance or correct audio.
- Add audio points to adjust the volume of specific areas of the waveform.

Edit Audio on the Timeline

Option	Details
Select audio on the timeline	Double-click a clip with audio. The clip turns green and the audio bar appears.
Silence a section of audio	Use the playhead to make a selection. Right-click the selection and choose Silence Audio . 
Add and move audio points to adjust volume of parts of a clip	Double-click on the audio bar to add points. Click and drag the audio points up, down, or across the audio bar. 

<p>Fade audio in or out</p>	<p>To create a fade, add three audio points to the audio bar. Drag points up or down to create the desired fade.</p>  <p>-OR-</p> <p>Click the Audio tab and drag the Fade In/Fade Out effects to the clip on the timeline.</p> <p>See Add Audio Effects (https://www.techsmith.com/learn/?post_type=tutorial&p=196578).</p>
<p>Delete audio points</p>	<p>Right-click an audio point and select Delete or Remove All Audio Points.</p> 
<p>Separate system audio from screen recording</p>	<p>Right-click audio and select Separate Video and Audio.</p>
<p>Change the look of the waveform (Windows only)</p>	<p>Select Edit > Preferences > Program tab > Mirror waveform.</p> 
<p>Save audio as M4A, MP3 (Windows only), or WAV</p>	<p>To export an audio file, select Share > Export Audio Only.</p> <p>See Export an Audio File (https://www.techsmith.com/blog/?post_type=tutorial&p=196536).</p>
<p>Apply Mix to Mono to have audio in both channels</p>	<p>Select audio clip on timeline and click Properties button > Audio subtab  > Mix to Mono checkbox.</p>
<p>Adjust audio level of all selected clips</p>	<p>Select audio clip on timeline and click Properties button > Audio subtab . Drag the Gain slider to adjust the clip's audio level.</p> <p>-OR-</p> <p>Drag the audio bar up or down.</p> 
<p>Adjust the audio level for the whole project</p>	<p>Click the volume indicator below the Properties button. Drag the slider to adjust the project's audio level.</p>




Add Audio Effects

Learn how to apply an audio effect to adjust the volume on different tracks, remove background noise, or even change the pitch of the speaker's voice.

Add and Edit Effects

1. Click the **Audio Effects** tab.




2. Drag an effect onto an audio clip on the timeline.


- To view applied effects, click the **Show Effects** tray icon on the media.



- To hide applied effects, click the **Hide Effects** tray icon on the media.



3. To adjust the duration, drag either end of the effect on the timeline.




4. To customize the effect, click **Properties**.



Note: Some effects have audio points instead of properties which are adjusted by clicking and dragging audio points on the track. See [Edit Audio \(https://www.techsmith.com/learn/?post_type=tutorial&p=182336\)](https://www.techsmith.com/learn/?post_type=tutorial&p=182336).

Effect Types

Effect	Customize Properties
<p>Audio Compression Helps even out audio levels.</p>	<ol style="list-style-type: none">1. Click Properties.2. Select a level from Volume variation dropdown menu or manually adjust Ratio, Threshold, and Gain to get the desired effect.
<p>Clip Speed Change audio and video clip to play back faster or slower.</p>	<p>Complete one of the following:</p> <ul style="list-style-type: none">• Click the Show Effects tray icon on the media and drag the effect handles on the timeline. • Click Properties and enter an amount for Speed or Duration to get the desired effect.<ul style="list-style-type: none">◦ Adjust speed higher for the video to play back faster.◦ Adjust speed lower for the video to play back slower.
<p>Emphasize Emphasizes the audio for the applied media by decreasing the volume of all other audio tracks.</p> <p>For example, apply the effect to voice-over audio to decrease the volume of the background music for the duration of the voice-over clip.</p>	<ol style="list-style-type: none">1. Click Properties.2. Drag the Emphasis slider to change the volume for all other audio tracks on the timeline. 100% mutes the audio of the other tracks for the duration of the applied clip.3. Select Ramp Position to set where the volume transition starts and ends on the timeline.<ul style="list-style-type: none">◦ Outside: Complete audio change before and after applied media. ◦ Span: Complete audio change over the start and end of the applied media. ◦ Inside: Complete audio change at the start of the applied media and before the end of the applied media. 

	<p>4. Enter an amount in seconds to set the duration the Ramp In and Ramp Out volume transitions occur.</p>
<p>Fade In / Fade Out Creates smooth transition in to or out of audio.</p>	<p>Automatically applied to beginning or end of audio clip. Grab audio points and drag to adjust.</p>
<p>Pitch (Mac Only) Adjust frequency of sound waves to change voice sound.</p>	<ol style="list-style-type: none"> 1. Click Properties. 2. Manually adjust Pitch, Ease In, or Ease Out to get desired effect.
<p>Noise Removal Helps reduce background noise.</p>	<ol style="list-style-type: none"> 1. Click Properties. 2. Click Analyze to automate noise removal process (Windows only) or manually adjust the Sensitivity, Reduction (Mac), or Amount (Windows) to get desired effect.

Add Text to Your Video

Follow our sample project to learn how to add and animate text, such as callouts, titles, lower-thirds, and calls-to-action, to a video.

Introduction

Add text to your videos to introduce your content, provide additional context or emphasis, engage viewers, or provide a call-to-action for viewers to discover your content, products, or recommended next steps.

In this video series, we will walk you through ways to add text in Camtasia. We have included an optional sample project for you to follow along and practice the concepts introduced in each video.

5 Ways to Add Text in Camtasia

Consider adding any of the following types of text to enhance the message and engagement in your videos:

1. Callout Annotations

Use callout text to provide additional context, emphasize areas, or as general text throughout a video.

▼ View Steps

1. Click the **Annotations** tab.
2. Click the **Callouts** subtab to browse the annotations available.
3. In the **Style** dropdown, select **All** to view all annotations.
4. Drag the annotation onto the timeline or canvas.
5. To edit callout text, double-click the callout on the canvas and enter the desired text.

To learn more about positioning and customizing annotations, see [Add Arrows, Shapes, or Callouts \(https://www.techsmith.com/learn/tutorials/camtasia/annotations/\)](https://www.techsmith.com/learn/tutorials/camtasia/annotations/).

2. Animate Text


Keep your viewers engaged in your videos by adding subtle visual effects and behaviors to animate text.

▼ View Steps


Add a Transition

1. Select the **Transitions** tab.
2. To find a transition, complete any of the following:


- Browse the list of transitions.
- To filter the list of transitions, select an option from the **Type** dropdown.
- Enter the transition name or type in the **Search** field.



3. Drag your cursor over the transition thumbnail to preview it.



4. Drag the transition onto media or annotations on the timeline.



The drop location on the media impacts where the transition is applied:

5. Drag to the left end of the media to apply the transition to the beginning of the clip.




6. Drag to the right end of the media to apply the transition to the end of the clip.



7. Drag to the middle of the media to apply the transition to both the beginning and the end.



8. To change the duration of the transition, drag the end of the transition in or out.




Tip: Drag the **Timeline** slider to make it easier to select and edit the transition.

9. Some transitions have additional properties you can customize. Click to select the transition on the timeline and click the **Properties** button to view the properties available.


See [Add a Transition \(https://www.techsmith.com/learn/tutorials/camtasia/video-transitions/\)](https://www.techsmith.com/learn/tutorials/camtasia/video-transitions/).

Add a Behavior


1. Click the **Behaviors** tab.



2. Drag a behavior animation onto media on the timeline.
3. Behaviors appear as an effect in the effects tray. Click to select the behavior in the effects tray.



4. Open the **Properties panel > Behaviors subtab.**



5. Edit the behavior properties for the In, During, and Out tabs.


See [Animate Text & Images with Behaviors \(https://www.techsmith.com/learn/tutorials/camtasia/animation-behaviors/\)](https://www.techsmith.com/learn/tutorials/camtasia/animation-behaviors/).

3. Lower-Thirds


These assets help introduce a speaker or scene in your video.

▼ View Steps


1. To access the free and premium assets in Camtasia version 2023.3.0 and later, select **Media tab > Camtasia Assets subtab.**




2. Complete any of the following:
 - Browse the assets in the **Titles** category. Click **See All** to view additional assets within that category.



- o Enter a search term, such as “Lower Third,” into the **Search** field and press the **Enter** key.



- o Click the **Search Filter** dropdown to filter the results by free assets, safe search, or your recent searches.



3. Double-click to preview an asset.
4. To add an asset to your video, drag the asset from the **Camtasia Assets** subtab onto the desired location on the timeline or canvas.


To learn more about customizing the asset, see [Enhance Your Video with Camtasia Assets](https://www.techsmith.com/learn/tutorials/camtasia/camtasia-assets/) (<https://www.techsmith.com/learn/tutorials/camtasia/camtasia-assets/>) or [Position Media on the Canvas](https://www.techsmith.com/learn/tutorials/camtasia/working-with-the-canvas/) (<https://www.techsmith.com/learn/tutorials/camtasia/working-with-the-canvas/>).

4. Titles


Similar to lower-thirds, add a title from Camtasia assets to introduce your video, a speaker, or scene.

▼ View Steps


1. To access the free and premium assets in Camtasia version 2023.3.0 and later, select **Media tab** > **Camtasia Assets subtab**.




2. Complete any of the following:
 - Browse the assets in the **Titles** category. Click **See All** to view additional assets within that category.



- o Enter a search term into the **Search** field and press the **Enter** key.



- o Click the **Search Filter** dropdown to filter the results by free assets, safe search, or your recent searches.



3. Double-click to preview an asset.
4. To add an asset to your video, drag the asset from the **Camtasia Assets** subtab onto the desired location on the timeline or canvas.


To learn more about customizing the asset, see [Enhance Your Video with Camtasia Assets](https://www.techsmith.com/learn/tutorials/camtasia/camtasia-assets/) (<https://www.techsmith.com/learn/tutorials/camtasia/camtasia-assets/>) or [Position Media on the Canvas](https://www.techsmith.com/learn/tutorials/camtasia/working-with-the-canvas/) (<https://www.techsmith.com/learn/tutorials/camtasia/working-with-the-canvas/>).

5. Outros + Call-to-Action

End your videos with a call-to-action that directs viewers to subscribe to your channel, view the next video in a series, or provide a link to purchase or sign up.


▼ View Steps

1. To access the free and premium assets in Camtasia version 2023.3.0 and later, select **Media tab** > **Camtasia Assets subtab**.




2. Complete any of the following:


- o Browse the assets in **Titles** and **Channel Kit** categories. Click **See All** to view additional assets within that category.



- o Enter a search term into the **Search** field and press the **Enter** key.



- o Click the **Search Filter** dropdown to filter the results by free assets, safe search, or your recent searches.



3. Double-click to preview an asset.
4. To add an asset to your video, drag the asset from the **Camtasia Assets** subtab onto the desired location on the timeline or canvas.

To learn more about customizing the asset, see [Enhance Your Video with Camtasia Assets](https://www.techsmith.com/learn/tutorials/camtasia/camtasia-assets/) (<https://www.techsmith.com/learn/tutorials/camtasia/camtasia-assets/>) or [Position Media on the Canvas](https://www.techsmith.com/learn/tutorials/camtasia/working-with-the-canvas/) (<https://www.techsmith.com/learn/tutorials/camtasia/working-with-the-canvas/>).

How to Add Captions in Camtasia

Captions display onscreen text synchronized with the voice-over and sounds in a video. Captions create videos accessible to a larger audience, including:

- Viewers who are deaf or hard of hearing.
- Viewers that cannot listen to audio in their current environment.
- Viewers who are non-native speakers by providing onscreen translations in the captions.

Camtasia allows you to create and publish two common video caption types:

Closed Captions

- Viewers can turn captions on or off in the video player controls.
- Help meet video accessibility guidelines.

See [Add Closed Captions to a Video](https://www.techsmith.com/learn/tutorials/camtasia/add-closed-captions/) (<https://www.techsmith.com/learn/tutorials/camtasia/add-closed-captions/>).


Dynamic Captions

- Always display onscreen as part of the video.
- Stylistic captions often used in social media videos or as a visual effect to enhance the video content or message.

See [Add Dynamic Captions](https://www.techsmith.com/learn/tutorials/camtasia/dynamic-captions/) (<https://www.techsmith.com/learn/tutorials/camtasia/dynamic-captions/>).


Time-Saving Text Tips

Follow these time-saving tips to help you create professional-looking videos for your brand, channel, or business.



Add Presets and Favorites

Add frequently-used or custom callout annotations as a preset. You can click the star icon on a callout to add it to your Favorites tab for quick access. See [Customize Camtasia](https://www.techsmith.com/learn/tutorials/camtasia/customize-camtasia/) (<https://www.techsmith.com/learn/tutorials/camtasia/customize-camtasia/>).



Save Custom Assets to Your Library

The library stores any custom assets or media you want to reuse across your Camtasia video projects. You can [package](https://www.techsmith.com/learn/tutorials/camtasia/package-share-camtasia-resources/) (<https://www.techsmith.com/learn/tutorials/camtasia/package-share-camtasia-resources/>) your library to share with others to:

- Maintain a consistent look and elements across videos.
- Help your team build professional videos based on your favorite video enhancements.
- Save time by having ready-made video elements easily accessible.

See [Reuse Media Across Projects \(Library\)](https://www.techsmith.com/learn/tutorials/camtasia/library/) (<https://www.techsmith.com/learn/tutorials/camtasia/library/>).



Apply a Theme

Set up your brand colors, font, and logo in a theme to quickly apply these presets to maintain consistency across a series of videos. See [Build Your Color Palette \(Themes\)](https://www.techsmith.com/learn/tutorials/camtasia/themes/) (<https://www.techsmith.com/learn/tutorials/camtasia/themes/>).

Visual Effects Overview


Apply effects to visually enhance your videos and engage your viewers.

Add a Visual Effect

Apply visual effects, for example to adjust color or change how media moves across the screen, without altering the original media. Effects can be applied to video clips and images, as well as objects such as text, callouts, and shapes.

To apply a visual effect:


1. Click the **Visual Effects** tab.






2. Drag an effect onto media on the timeline.

Edit a Visual Effect

Click the **Effects** tray on the media and click to select the effect. The effect turns yellow.




Option	Description
Adjust the Properties	Click the Properties button to view and adjust the effect settings in the properties panel. 
Turn Off and On	Click the toggle in the properties panel. 
Adjust the Duration	Drag the effect handles to adjust when the effect starts and ends during the clip. 




Option	Description
Delete the Effect	<p>Press the Delete key or click the X icon in the properties panel.</p> 

Visual Effect Types


- [Color Effects](#)
- [Graphic Display Effects](#)
- [Motion Effects](#)
- [Multi-Track Effects](#)

Color Effects

Effect	Details
Color Adjustment	<p>Adjust the brightness, contrast, and saturation settings of an image or video in the properties panel.</p> 
Color LUT	<p>Apply the default Color Lookup Table (LUT) to enhance color contrast, or import Color LUT files to apply other color grading treatments.</p> 
Color Filters	<p>Preview and apply a unique Color LUTs to an image or video. See Edit Video Colors and Shading (Filters) (https://www.techsmith.com/learn/tutorials/camtasia/filters/).</p>
Color Tint	<p>Apply one color to light tones and a second color to dark tones in a video or image.</p>

Effect	Details
	
Colorize	<p>Apply a single color overlay to media.</p> 
Glow	<p>Apply a glowing effect to light areas of media.</p> 
Remove a Color	<p>Remove a single-color background to substitute a different background image or video.</p>  <p>See Remove a Color (Green Screen) (https://www.techsmith.com/learn/tutorials/camtasia/how-to-remove-a-color/).</p>
Sepia (Mac)	<p>Apply a sepia tone to media.</p> 

Graphic Display Effects

Effect	Details
Background Removal	<p>Remove your background, even complex or multi-color backgrounds, without needing to use green screen. This visual effect works best when there is a single person or primary object on the screen.</p> <p>See Remove a Background from Your Video (https://www.techsmith.com/learn/tutorials/camtasia/video-background-removal/).</p>
Blur Region	<p>Add a rectangular or oval blur to hide confidential or distracting content, to make a title screen, or to create new effects.</p>  <p>See Blur or Mask a Video (https://www.techsmith.com/learn/tutorials/camtasia/blur-mask-video/).</p>
Border	<p>Add a color border around the media.</p> 
Corner Rounding	<p>Round one or more corners.</p> 
Cursor Path Creator	<p>Add a cursor path to images or to video not recorded with Camtasia.</p> 

Effect	Details
--------	---------

See [Customize Your Cursor and Path](https://www.techsmith.com/learn/tutorials/camtasia/customize-your-cursor-path-2/) (https://www.techsmith.com/learn/tutorials/camtasia/customize-your-cursor-path-2/).



Display media within the frame of a laptop, mobile device, or computer display.



See [Provide Context with Device Frames](https://www.techsmith.com/learn/tutorials/camtasia/device-frames/) (https://www.techsmith.com/learn/tutorials/camtasia/device-frames/).




Apply a drop shadow to give media a 3D effect on the canvas. Specify the shadow color and angle.

Keystroke (Mac) Automatically display key combinations pressed during recording that included the Command, Option, or Control modifier key.



Note: This effect can only be applied to screen recordings captured with Camtasia (TREC files).


Effect	Details
	<p data-bbox="365 163 1458 237">Tip: On Windows, manually add keystrokes as annotations.</p> <p data-bbox="418 279 1372 352">Select Annotations tab > Keystroke Callouts subtab , and drag a callout onto the timeline. Edit the key combination in the properties panel.</p>
Mask	<p data-bbox="334 451 1469 478">Reveal only an oval or rectangular portion of media, or invert the mask to hide a portion of the media.</p> <div data-bbox="334 520 1300 779">  </div>
Interactive Hotspot	<p data-bbox="334 814 1404 884">Add a clickable call-to-action to link to a webpage, automatically pause video, or direct users to replay or jump to a different section of your video.</p> <div data-bbox="334 926 818 1245">  </div> <p data-bbox="334 1283 1404 1352">See Add Hotspots (Interactive Videos) (https://www.techsmith.com/learn/tutorials/camtasia/add-interactive-hotspots-to-a-video/).</p>
Mosaic (Mac)	<p data-bbox="334 1394 803 1421">Pixelates media to create a mosaic effect.</p> <div data-bbox="334 1463 1300 1722">  </div>
Outline Edges	<p data-bbox="334 1757 1091 1785">Automatically apply the effect of a line drawing to a video or image.</p>

Effect	Details
	
Reflection	<p data-bbox="334 436 1068 464">Add a reflection to media that does not take up the entire canvas.</p>  <div data-bbox="334 1031 1479 1220" style="background-color: #f0f0f0; padding: 10px; border-left: 3px solid #008000;"> <p data-bbox="423 1094 1386 1157">Note: To reflect grouped objects individually, ungroup the objects first and then apply the Reflection effect.</p> </div>
Spotlight	<p data-bbox="334 1272 997 1299">Create the appearance of a spotlight shining on the media.</p> 
Tiling	<p data-bbox="334 1633 1344 1696">Repeat a logo, image, or video in a pattern across the screen to create a custom animated background.</p> 

Effect	Details
	<p>To customize the Tiling effect, complete any of the following:</p> <ul style="list-style-type: none"> • In the properties, adjust the Scale. • Drag the control points on the canvas to adjust the vertical and horizontal position of the tiles. • For a watermark effect, decrease the Opacity in the properties. • To scroll the pattern across the canvas, apply an animation to the media. See Animations In-Depth (https://www.techsmith.com/learn/tutorials/camtasia/animations-in-depth/). 
Window Spotlight (Mac)	<p>Automatically dim all inactive windows in a screen recording to draw attention to the active window.</p>  <p>Note: This effect can only be applied to screen recordings captured with Camtasia (TREC files).</p>
Vignette	<p>Add a fade to an image or video without a defined border.</p> 

Motion Effects


Effect	Details
Clip Speed	<p>Play a video clip faster or slower than its original pace.</p>  <p>See Speed Up & Slow Down Video Clips (https://www.techsmith.com/learn/tutorials/camtasia/clip-speed/).</p>
Freeze Region	<p>Fix one area of a video on the canvas while the remaining area continues to play. See Freeze a Region.</p> 
Motion Blur	<p>Blurs objects that have animation (https://www.techsmith.com/learn/tutorials/camtasia/animations-in-depth/) applied to them.</p>  <p>Note: Motion Blur does not affect movement in video clips.</p>

Effect	Details
<p>Motion Path</p>	<p>Add movement to objects such as annotations, images, and clips, to make them arc, swoop, or glide across the screen.</p>  <p>See Add Movement to Any Object (Motion Path) (https://www.techsmith.com/learn/tutorials/camtasia/motion-path/).</p>


Freeze a Region

Freeze screen content in the selected area while the video continues to play to remove mistakes such as a notification.


1. Click the **Visual Effects > Visual Effects** tab.





2. Drag **Freeze Region** onto the media on the canvas or timeline.
3. A portion of the screen is selected. Drag the selection to the location on the screen to hide your unwanted content. You can adjust the size by grabbing the surrounding handles.



4. Click and drag the effect end points on the timeline to adjust the duration of the Freeze Region effect.



Multi-Track Effects

Effect	Details
Blend Mode	<p>Choose from dozens of modes to custom blend an image or video with media on the track(s) below.</p> <div style="display: flex; align-items: center; justify-content: center;">  +  + <div style="text-align: center;"> <p>Darken Mode =</p>  </div> <div style="margin-left: 20px;"> <p>Lighten Mode =</p>  </div> <div style="margin-left: 20px;"> <p>Vivid Light Mode =</p>  </div> </div>
Media Matte	<p>Simplifies adding a track matte or “masking” to display or hide media on the tracks below.</p> <div style="display: flex; align-items: center; justify-content: center;">  +  =  </div> <p>See Create Stunning Animations with Media Mattes (https://www.techsmith.com/learn/tutorials/camtasia/animations-with-media-mattes/).</p>


Add Arrows, Shapes, & Callouts

Learn how to enhance your video and focus viewers' attention with annotations, including callouts, arrows, lines, shapes, blur, and keystrokes.

Annotations Overview


Annotations are visual elements and text to emphasize, direct viewers' attention, provide additional information, or cover up areas in your video.

Camtasia includes six types of annotations:




Callouts

Add a callout to display onscreen text, titles, and lower-thirds, or to focus viewers' attention.




Blur & Highlight

Add a blur to cover up an area or a highlight to emphasize an area.




Arrows & Lines

Add arrows to point out areas or lines to add visual elements.




Sketch Motion Callouts

Add an animated callout to give the appearance of drawing on the screen to highlight specific areas.



Shapes

Add shapes as a visual elements or to cover up areas.



Keystroke Callouts

Add callouts to display keyboard shortcuts mentioned in your video.

1. Add an Annotation

1. Click the **Annotations** tab.
2. Click a subtab to browse the annotations available for each type.
3. In the **Style** dropdown, select **All** to view all annotations.
4. Drag the annotation onto the timeline or canvas.

Note: Additional callouts are available in the Camtasia Assets. To browse these assets, select **Media tab > Camtasia Assets subtab > Callouts > See All**. See [Enhance Your Video with Camtasia Assets \(https://www.techsmith.com/learn/tutorials/camtasia/camtasia-assets/\)](https://www.techsmith.com/learn/tutorials/camtasia/camtasia-assets/).

2. Position the Annotation

The timeline displays the sequence of all media in a video. The timeline playhead displays the current frame in the video.

To position when the annotation appears in your video:

1. Drag the annotation to where you want the annotation to start on the timeline.
2. To edit the duration, drag the end of the annotation in or out. The default duration is five seconds.

The canvas is the video preview area. On the canvas, set the desired position and size for the annotation. Complete any of the following edits on the canvas to position media in your video:

Move

Click and drag the annotation to move to a new location on the canvas.

Resize / Scale

Click to select the annotation on canvas. Drag a corner handle in or out.

Rotate

Click to select media on canvas. Drag the center handle in the annotation to rotate around the anchor point.

Align


The canvas offers boundary guidelines to help you snap objects to the edge or center of the canvas, or align with other media or annotations.

- **Canvas Guides:** The guides appear as you drag media on the canvas. Drag media until it aligns with the edge or center of the canvas, or other media guidelines.
- **Ruler Guides:** See [Align Media with Ruler Guides \(https://www.techsmith.com/learn/?post_type=tutorial&p=241938\)](https://www.techsmith.com/learn/?post_type=tutorial&p=241938).

Edit Callout Text

Double-click the callout on the canvas and enter the desired text.

3. Customize the Annotation



1. Click to select the annotation on the timeline or canvas.
2. Click the **Properties** button to customize the settings available for the annotation such as color, text, and style.
3. Based on the annotation selected, the properties panel displays the following tabs:

- **Visual properties tab**




: Fine tune edits on the canvas with properties such as scale, opacity, position, and rotation.

- **Text properties tab**



: Edit the font, style, and colors for the annotation text.

- **Annotation properties tab**



: Edit properties specific to the selected annotation type such as style and color. For example, enter the keystrokes to display for Keystroke annotations or set the draw time for Sketch Motion callouts.

4. To quickly change a set of properties for a consistent look, style, or brand across videos, select a theme from the **Theme** dropdown. See [Build Your Color Palette \(https://www.techsmith.com/learn/tutorials/camtasia/themes/\)](https://www.techsmith.com/learn/tutorials/camtasia/themes/).
5. As you edit the properties, the canvas shows a preview of the changes. To learn more, see [Discover the Properties Panel \(https://www.techsmith.com/learn/tutorials/camtasia/media-properties/\)](https://www.techsmith.com/learn/tutorials/camtasia/media-properties/).


Tip: Save annotations for reuse.

Add a custom annotation to your list of Favorites or preset annotations. See [Customize Camtasia \(https://www.techsmith.com/learn/tutorials/camtasia/customize-camtasia/\)](https://www.techsmith.com/learn/tutorials/camtasia/customize-camtasia/).

4. Enhance the Annotation

Apply animations, transitions, behaviors, or visual effects to enhance or animate annotations.

For example, to animate an annotation similar to the example above, drag a **Slide Right** transition to the start of the callout and a **Slide Left** transition to the end.



To learn more, see the following tutorials:

- [Animations In-Depth \(https://www.techsmith.com/learn/tutorials/camtasia/animations-in-depth/\)](https://www.techsmith.com/learn/tutorials/camtasia/animations-in-depth/)
- [Animate Text & Images with Behaviors \(https://www.techsmith.com/learn/tutorials/camtasia/animation-behaviors/\)](https://www.techsmith.com/learn/tutorials/camtasia/animation-behaviors/)

Get Inspired

Check out these tutorials to continue to build your skills and discover new ways to use annotations in your videos:

- [Blur or Mask a Video \(https://www.techsmith.com/learn/tutorials/camtasia/blur-mask-video/\)](https://www.techsmith.com/learn/tutorials/camtasia/blur-mask-video/)
- [Enhance Your Video with Camtasia Assets \(https://www.techsmith.com/learn/tutorials/camtasia/camtasia-assets/\)](https://www.techsmith.com/learn/tutorials/camtasia/camtasia-assets/)
- [Set the Background Color with a Shape Annotation \(https://www.techsmith.com/learn/tutorials/camtasia/working-with-the-canvas/#h-change-the-background-color\)](https://www.techsmith.com/learn/tutorials/camtasia/working-with-the-canvas/#h-change-the-background-color)
- [Create a Rounded Image or Webcam with Shape + Media Matte Effect \(https://www.techsmith.com/learn/tutorials/camtasia/audio-visualizers/#h-add-an-avatar-webcam-or-icon\)](https://www.techsmith.com/learn/tutorials/camtasia/audio-visualizers/#h-add-an-avatar-webcam-or-icon)

Add a Dynamic Background

Add looping animated backgrounds with customizable colors, speeds, and more.

Dynamic Backgrounds add looping animations with customizable colors, speeds, and more to the background of your video.

Advantages of Dynamic Backgrounds

Here are three advantages to using a dynamic background vs. a traditional motion background:

1. Smaller File Size

High-definition versions of traditional motion backgrounds have large file sizes. Dynamic backgrounds, with their smaller file sizes, allow you to use up less space on your hard drive and more space for your content.

2. Seamless Looping & Unlimited Duration

Traditional motion backgrounds are usually a video file with a fixed length. It can be challenging to line up the beginning and end of the motion graphic clips to create a seamless loop. With dynamic backgrounds, you can customize to any duration by simply dragging the ends of the background on the timeline to the desired length, whether it's 10 seconds or 10 minutes.

3. Customizable

With traditional motion backgrounds, it's not possible to adjust the colors, speed, or other visual settings. Each dynamic background has its own set of customizable properties. Explore the settings across the dynamic backgrounds in the [properties](https://www.techsmith.com/learn/tutorials/camtasia/media-properties/) (<https://www.techsmith.com/learn/tutorials/camtasia/media-properties/>).

3 Use Cases for Dynamic Backgrounds

Discover some applications for dynamic backgrounds to create the desired effect and make your professional videos stand out:

Enhance Your Titles & Intros

Add a dynamic background behind your title, outro, or call-to-action to enhance and draw attention to otherwise static, boring screens in your video.

Frame Your Screen Content


Draw viewers' attention to screen content by visually framing a screen recording with colors and animations around content.

Add Motion for Visual Effect


Dynamic graphics provide motion to emphasize a point, visually engage and excite users, or create flow through the video's transitions.

Add a Dynamic Background

1. Select **Media tab > Camtasia Assets subtab > Dynamic Backgrounds > See All**.




2. Browse or search for a dynamic background. Double-click an asset to preview it.
3. Drag a dynamic background onto the timeline. If you already have content on your timeline, drag the background onto a track below the other timeline content in order for it to appear behind this content in the video.




4. Click **Properties** to open the Properties panel.



5. Each dynamic background has its own set of customizable properties, such as color, size, and speed. Edit the desired properties in the **Dynamic Properties** section.



6. To change the duration, drag the end of the dynamic background in or out on the timeline.



Tip: Layer Multiple Dynamic Backgrounds to create a custom look.

You can layer backgrounds on top of each other. Drag two dynamic background onto the timeline. And then, drag a visual effect, such as the Blend Mode effect, onto the dynamic background on the top track on the timeline. Experiment with adding different effects to the layered backgrounds.

Create the Illusion of 3D Perspective (Corner Pinning)

Learn how to pin and adjust a video, image, or text on background media to create the illusion of 3D perspective.

- Make it look like your video is running on a computer or mobile device screen
- Place an image or text on a moving surface
- Simulate text painted on an angled wall

Quickly integrate a video, image, or text with a background in Corner Pin mode. Use corner pinning to:



Pin Media or Text

Complete the following to pin media or text to the canvas to integrate it with a background:

1. Drag a video or image onto the timeline to use as the background media.
2. Drag a video, image, or text from the [Media Bin](https://www.techsmith.com/learn/tutorials/camtasia/import-manage-media/), [Camtasia Assets](https://www.techsmith.com/learn/tutorials/camtasia/camtasia-assets/), [Library](https://www.techsmith.com/learn/tutorials/camtasia/library/), or [Annotations](https://www.techsmith.com/learn/tutorials/camtasia/annotations/) tab to a timeline track above the background media. This will be the foreground media.
3. With the foreground media selected, click **Corner Pin Mode** in the canvas toolbar to enable corner pinning.



4. On the canvas, drag a corner of the selected media to the desired position.



Note: Camtasia automatically updates position, skew, rotation, and other properties in the [Properties panel](https://www.techsmith.com/learn/tutorials/camtasia/media-properties/) (<https://www.techsmith.com/learn/tutorials/camtasia/media-properties/>).

5. Repeat step 4 for the remaining corner handles.


Tips

- For precise pinning, use the magnification controls and  mode in the canvas toolbar to get a close-up view of corners. See [Position Media on the Canvas](https://www.techsmith.com/learn/tutorials/camtasia/working-with-the-canvas/) (<https://www.techsmith.com/learn/tutorials/camtasia/working-with-the-canvas/>).
- Press **Control** while dragging corners to temporarily disable snapping.
- Add animation to pinned objects to match them to the motion of background video. See [Animations In-Depth](https://www.techsmith.com/learn/tutorials/camtasia/animations-in-depth/) (<https://www.techsmith.com/learn/tutorials/camtasia/animations-in-depth/>).

Remove a Background from Your Video

Learn how to automatically remove the background from Camtasia recordings or imported media.

Apply the **Background Removal** effect to instantly remove the background from your camera recordings.




Consider removing the background when:

- The camera video was not recorded in the ideal environment, such as at home or in a setting that distracts from your video content.
- You want to simplify your content to focus on the subject of your video.
- The webcam covers up key parts of the screen recording or your video content.
- You want to adjust your video layout to set the tone or maintain viewer engagement.


Remove a Background in Camtasia Rev

After recording, you can apply the **Background Removal** effect in Camtasia Rev in the following ways:

- Select a layout with Background Removal automatically applied.



- On the Effects tab, select **Background Removal**.



Note: You can turn off some of the automatic selections in Camtasia Rev, such as backgrounds. Click to deselect the option on the **Background**, **Effects**, or **Filters** tabs.

Remove a Background in Camtasia Editor

1. In Camtasia Editor, select the **Visual Effects** tab.
2. Drag the **Background Removal** effect onto media on the timeline.
3. In the Properties panel, edit the settings to customize the effect.

Tip: Replace the background with a dynamic background for a professional video look.

To learn how to add and customize a dynamic background, see [Add a Dynamic Background \(https://www.techsmith.com/learn/tutorials/camtasia/dynamic-backgrounds/\)](https://www.techsmith.com/learn/tutorials/camtasia/dynamic-backgrounds/).

Background Removal Recording Tips

Follow these tips during recording to achieve the best results for the Background Removal effect:

1. Use good lighting.




2. Choose clothing that does not blend in with your background.



3. Avoid fast movements.



4. Use a chair with a lower back if possible.



Enhance Your Video Overview


Add enhancements to apply effects, animations, behaviors, transitions, and annotations that can make your video look more polished and professional.

Video Enhancement Types

Type	Description
Animations	<p>Animations add interesting focal points to your video such as:</p> <ul style="list-style-type: none">• A talking head that smoothly transitions or trades places with a screen recording.• An image that enters the video from the left, pauses, then flies off the canvas to the right.• Callouts that animate in various ways on the canvas to draw attention to an area in the video.• Zooming in or out on important parts of your video to draw attention to key actions or enhance difficult to view parts within a video. <p>Add animations to images, video clips, and annotations. To learn more about editing annotations, see Edit Enhancements.</p> <ul style="list-style-type: none">• Animations In-Depth (https://www.techsmith.com/learn/tutorials/camtasia/animations-in-depth/)• Animate Text & Images with Behaviors (https://www.techsmith.com/learn/tutorials/camtasia/animation-behaviors/)• Zoom In to Focus Attention (https://www.techsmith.com/learn/tutorials/camtasia/animations/)
Annotations and Text	<p>Graphics or text overlaid on a video to draw viewers' attention to important objects or processes. To learn more about editing annotations, see Edit Enhancements.</p> <ul style="list-style-type: none">• Add Annotations, Callouts, & Titles (https://www.techsmith.com/learn/tutorials/camtasia/annotations/)• Edit Media on the Canvas (https://www.techsmith.com/learn/tutorials/camtasia/edit-canvas/)• Blur or Mask a Video (https://www.techsmith.com/learn/tutorials/camtasia/blur-mask-video/)
	<p>Behaviors are animated presets to drag and drop on text and media to liven it up and engage your viewers. Apply behaviors to any visual object on the timeline.</p> <p>These might include:</p> <ul style="list-style-type: none">• Plain text that gently pulsates where you want viewers to click a link.• Image or a logo that enters the screen then swings back and forth on a hinge.

Behaviors	<ul style="list-style-type: none"> • Callouts that animate in various ways on the canvas to draw attention to an area in the video. <p>See Animate Text & Images with Behaviors (https://www.techsmith.com/learn/tutorials/camtasia/animation-behaviors/) and Add Annotations, Callouts, & Titles (https://www.techsmith.com/learn/tutorials/camtasia/annotations/).</p>
Cursor Effects	<p>Camtasia Recorder collects and stores cursor data in the TREC recording file. Add cursor effects to enhance or edit the cursor in your recording.</p> <ul style="list-style-type: none"> • Edit the Cursor with Effects (https://www.techsmith.com/learn/tutorials/camtasia/cursor-effects/) • Quickly Smooth Cursor Movements (https://www.techsmith.com/learn/tutorials/camtasia/cursor-smoothing/)
Transitions	<p>Transitions add a visual effect between the end of a clip and the beginning of the next clip. Use transitions to indicate the passage of time, change in location, or to create a smooth flow between clips.</p>
Visual Effects	<p>Visual effects can improve the look and quality of your video. Apply an effect to an entire clip or adjust the duration to a portion of a clip.</p> <ul style="list-style-type: none"> • Visual Effects Overview (https://www.techsmith.com/learn/tutorials/camtasia/visual-effects/) • Add Hotspots (Interactive Videos) (https://www.techsmith.com/learn/tutorials/camtasia/add-interactive-hotspots-to-a-video/) • Create Stunning Animations with Media Mattes (https://www.techsmith.com/learn/tutorials/camtasia/animations-with-media-mattes/) • Provide Context with Device Frames (https://www.techsmith.com/learn/tutorials/camtasia/device-frames/) • Remove a Color (Green Screen) (https://www.techsmith.com/learn/tutorials/camtasia/how-to-remove-a-color/) • Speed Up & Slow Down Video Clips (https://www.techsmith.com/learn/tutorials/camtasia/clip-speed/)
Gesture Effects (Mac only)	<p>Gesture effects add visual effects that simulate taps, swipes, and pinches on mobile devices. See Record iOS Devices (https://www.techsmith.com/learn/tutorials/camtasia/recording-your-ios-device/).</p>

Add an Enhancement



1. Click an enhancement tab, such as the Annotations tab or Behaviors tab.
2. Select an enhancement from the subtabs or dropdowns.
3. Drag the enhancement onto the timeline. For some enhancements, Camtasia highlights where the selection can be applied.
4. To edit the properties, see [Discover the Properties Panel](https://www.techsmith.com/learn/tutorials/camtasia/media-properties/) (<https://www.techsmith.com/learn/tutorials/camtasia/media-properties/>).

Tip: Save custom enhancements to reduce editing time.

Save custom enhancements as presets or favorites to streamline your workflow. See [Customize Camtasia](https://www.techsmith.com/learn/tutorials/camtasia/customize-camtasia/) (<https://www.techsmith.com/learn/tutorials/camtasia/customize-camtasia/>).


Edit Enhancements

Type	Details
	<p>Click to select the animation arrow to edit. The selected animation arrow turns yellow.</p> <ul style="list-style-type: none"> • Change duration: Drag the end of the animation in either direction. 

- **Move:** Click and drag the animation arrow onto another location on the media on the timeline.



- **Restore:** Drag the **Restore** animation onto a clip after another animation to reverse the previous animation to its previous state.



- **Delete:** Press the **Delete** key.

For more editing help, see [Animations In-Depth](https://www.techsmith.com/learn/tutorials/camtasia/animations-in-depth/) (<https://www.techsmith.com/learn/tutorials/camtasia/animations-in-depth/>) and [Zoom In to Focus Attention](https://www.techsmith.com/learn/tutorials/camtasia/animations/) (<https://www.techsmith.com/learn/tutorials/camtasia/animations/>).

Animations

Annotations and Text

Click to select the annotation to edit.

- **Edit text:** Double-click the annotation on the canvas and enter the desired text.
- **Move:** Click and drag the annotation to new location on the canvas.
- **Resize:** Click and drag a handle in any direction.
- **Rotate:** Click and drag the center handle.
- **Delete:** Press the **Delete** key.


For more editing help, see [Add Annotations, Callouts, & Titles](https://www.techsmith.com/learn/tutorials/camtasia/annotations/) (<https://www.techsmith.com/learn/tutorials/camtasia/annotations/>).

Click the Effects tray on the media and click to select the behavior. The selected behavior turns yellow.




In the properties panel:

- **Turn on/off:** Click the toggle to turn the behavior on or off.



- **Delete:** Click the **X** icon to remove the behavior.



- **In tab:** Customize how the behavior enters the canvas.
- **During tab:** Customize the behavior while it is on the canvas.
- **Out tab:** Customize how the behavior exits the canvas.


For more editing help, see [Animate Text & Images with Behaviors](https://www.techsmith.com/learn/tutorials/camtasia/animation-behaviors/) (<https://www.techsmith.com/learn/tutorials/camtasia/animation-behaviors/>) and [Add Annotations, Callouts, & Titles](https://www.techsmith.com/learn/tutorials/camtasia/annotations/) (<https://www.techsmith.com/learn/tutorials/camtasia/annotations/>).

Behaviors

Click the Effects tray on the media and click to select the effect. The effect turns yellow.



- **Change duration:** Drag the effect handles to adjust when the effect starts and ends during the clip.



- **Delete:** Press the **Delete** key to remove the behavior or effect.
- **Edit properties:** Adjust the settings in the properties panel.
- **Turn on/off:** Click the toggle in the properties panel.

For more editing help, see [Edit the Cursor with Effects](https://www.techsmith.com/learn/tutorials/camtasia/cursor-effects/) (<https://www.techsmith.com/learn/tutorials/camtasia/cursor-effects/>), [Record iOS Devices \(Mac\)](https://www.techsmith.com/learn/tutorials/camtasia/recording-your-ios-device/) (<https://www.techsmith.com/learn/tutorials/camtasia/recording-your-ios-device/>), and [Visual Effects Overview](https://www.techsmith.com/learn/tutorials/camtasia/visual-effects/) (<https://www.techsmith.com/learn/tutorials/camtasia/visual-effects/>).

Cursor Effects, Gesture Effects, and Visual Effects

Transitions

Click to select the transition on the timeline. The transition turns yellow.

- **Change duration:** Drag the transition handles on the timeline to adjust when the transition starts and ends.



- **Edit properties:** Adjust the settings in the properties panel.
- **Turn on/off:** Click the toggle in the properties panel.
- **Delete:** Press the **Delete** key.


Tip: Improve editing performance with Proxy Video.

If you experience lag, particularly when playing back or scrubbing through high-resolution video, create a Proxy Video to improve performance. See [Import & Manage Your Media \(Media Bin\)](https://www.techsmith.com/learn/tutorials/camtasia/import-manage-media/) (<https://www.techsmith.com/learn/tutorials/camtasia/import-manage-media/>).


Edit Video Colors and Shading (Filters)

Learn how to adjust the tone and feel of your content with filters or color lookup tables (Color LUTs).


Give your content a cinematic color tone, a vintage feel, or a futuristic look. Or apply filters to correct and match lighting between different pieces of media.



1. Click **Visual Effects > Filters** tab.



2. Drag a filter onto media on the canvas or timeline.
3. Click **Properties** to open the Properties panel.



4. Adjust Color LUT properties as needed:

- o **LUT:** Select an option from the dropdown to change the applied filter.
Tip: Hover over options in the LUT dropdown to preview each filter on your media on the canvas.
- o **Intensity:** Drag the slider or enter a percentage value to adjust all color settings together.
- o **Range:** Select a blend range preset from the dropdown or click the  icon to show advanced blending range controls.
- o **Ease In / Ease Out (Mac only):** Enter an amount in seconds to transition the start or end of the filter.

5. Click  in the properties panel to add your customized color LUT to the Filters tab.

Quickly Smooth Cursor Movements

The Cursor Smoothing effect transforms cursor movements in screen recordings to smooth lines.

Note: The Cursor Smoothing effect can only be applied to screen recordings captured with Camtasia. Once the recording clip is on the timeline, the effect may be applied.

Add Cursor Smoothing Effect

1. Select the **Cursor Effects** tab.
2. Drag the **Cursor Smoothing** effect to the desired clip on the timeline.
3. Edit settings in the Properties panel. See [Edit Cursor Smoothing Properties](#).

Edit Cursor Smoothing Length and Timing

1. With the Cursor Smoothing effect applied, click the **Show Effects** tray icon on the media.




2. Click and drag the right or left edge of the effect to adjust the length.
3. Click and drag to reposition the effect in the clip.

Tip: Smooth the cursor at multiple points in the clip.

To apply the effect to multiple sections of the same clip, click and drag the effect to the clip again. Then adjust the length and position.

Edit Cursor Smoothing Properties

Customize the settings for the Cursor Smoothing effect in the Properties panel.



- **Duration:** The amount of time it takes the cursor to move from one point to the next.
- **Delay:** The amount of time the cursor pauses before and after each click.
- **Easing:** Slows the cursor down as it approaches an endpoint and gradually accelerates the cursor as it leaves. Easing gives the cursor a natural looking motion.
- **Detect Cursor Pauses:** If enabled, Camtasia will recognize when the cursor is stationary for one second or longer and display the pause in the cursor path. When disabled, only clicks will be registered as points on the cursor path.

Provide Context with Device Frames

Add a device frame around an image or video clip to provide context and a professional look to your video.




Device frames are great for:


- Introducing a scene such as a mobile or desktop demo.
- Showing your company's website within a product marketing video.

Add a Device Frame

1. Click the **Visual Effects** tab.



2. Drag the **Device Frame** effect onto an image or clip on the timeline.
3. Click the **Properties** button to open the properties.
4. In the properties, select a device frame from the **Type** dropdown.




5. Device frames fit media with a 16:9 aspect ratio and will fill standard video dimensions such as 1080p and 720p. If a device frame doesn't fill the entire canvas. Click and drag the edges of the clip until it snaps to the borders on the canvas.

Note: To download more device frames, select the **Download More** option in the **Type** dropdown or go to <https://library.techsmith.com/Camtasia> (<https://library.techsmith.com/Camtasia>).

Remove a Device Frame

In the properties, click the X icon.



Remove A Color (Green Screen)


Learn how to remove a single-color background from a video with the Remove a Color effect.

Record your subject in front of a single color backdrop, add the Remove a Color effect, and then replace the background with other media. This is also known as green screen or chromakey.



Note: Download our [sample green screen video](https://assets.techsmith.com/Downloads/ua-tutorials-camtasia-9-3/green-screen-video-for-download.mp4) (<https://assets.techsmith.com/Downloads/ua-tutorials-camtasia-9-3/green-screen-video-for-download.mp4>) to practice applying this effect. Click the options button in the bottom-right corner of the sample video and select **Download**.

1. Click the **Visual Effects** tab.




2. Drag the **Remove a Color** effect onto media on the timeline.




3. Click the **Properties** button to open the properties.

4. In the properties, click the **Color** dropdown and click the **Eyedropper** button to select the color to remove from the media on the canvas.




5. Adjust the following properties to continue editing the color removal:



- **Tolerance:** Drag the slider to increase or decrease the range of tints and shades for the selected color.
- **Softness:** Drag the slider to smooth out pixelation and rough edges of color around the subject.
- **Defringe:** Drag the slider left or right to make any remaining color less noticeable.
- **Hue:** Drag the slider to adjust the color of the clip to better match a new background.
- **Invert:** Select to reverse the color removal and hide everything except the color removed.

6. To add a new background, drag media onto the track below the edited clip.




Speed Up & Slow Down Video Clips


Learn how to speed up or slow down media on the timeline.

Clip speed allows you to play a video clip faster or slower than its natural pace.


1. Click **Visual Effects** tab.




2. Drag the **Clip Speed** effect onto media on the timeline.




3. Select the media with the clip speed applied and click the arrow on the bottom of the clip to open the Effects tray.



4. Select **Clip Speed** in the Effects tray and complete one of the following:
 - o Drag the clip speed handles to adjust the speed of the clip.



- o Click the **Properties** button to adjust the **Duration** and **Speed** to get the desired effect.



- Increase the speed to play back the video faster.
- Decrease the speed to play back the video slower.

Tip: Split media first to adjust the speed of different segments.

To vary the duration and speed of different parts of the media, split the media first before applying the Clip Speed effect. To learn more about splitting media, see [Remove Mistakes \(Trim & Split\)](https://www.techsmith.com/learn/?post_type=tutorial&p=182315) (https://www.techsmith.com/learn/?post_type=tutorial&p=182315).

Add a Transition

Learn how to add a transition between video clips or to animate text, annotations, or objects in your video.

Transitions Overview

Add transitions to apply visual changes between clips or animate the appearance of elements in your video. Transitions can be applied to media, annotations, text, and assets on the timeline.

Common Uses for Transitions

Camtasia has over 175 transitions available. Play around to find your favorites. Here are some recommended uses for transitions in a video to get you started:

Passage of Time

Convey some time has passed, such as when a download has occurred or the video does not show the entire process.

Try a Gradient Wipe, Card Flip, or Card Swipe.

Switch Context

Signify a change in context. For example, demonstrate switching between applications in a recording or between sections in your video.

Try a Cube Rotate, Swap, or Card Flip.

Smooth Transition

Ease the transition between scenes or the sudden appearance of objects, such as arrows, in your video.

Try a Fade.

Animate Media or Objects

Create movement for elements in your video.

Try a Slide Left or Slide Right.

Artistic Visual Effect


Achieve a specific visual effect to convey the message or tone in the video. For example, Snapshot is great for a photograph effect, and Glitch can convey the feeling of an old video or throwback.

These are best used sparingly in a video and to serve a specific purpose.


Add a Transition

1. Select the **Transitions** tab.
2. To find a transition, complete any of the following:
 - o Browse the list of transitions.
 - o To filter the list of transitions, select an option from the **Type** dropdown.


- o Enter the transition name or type in the **Search** field.



3. Drag your cursor over the transition thumbnail to preview it.



4. Drag the transition onto media or annotations on the timeline.



5. The drop location on the media impacts where the transition is applied:

- o Drag to the left end of the media to apply the transition to the beginning.




- o Drag to the right end of the media to apply the transition to the end.



- o Drag to the middle of the media to apply the transition to both the beginning and the end.



6. To change the duration of the transition, drag the end of the transition in or out.




Tip: Drag the **Timeline** slider to make it easier to select and edit the transition.

7. Some transitions have additional properties you can customize. Click to select the transition on the timeline and click the **Properties** button to view the properties available.

Best Practices

- Transitions can help you create the perfect visual transition or effect, but adding too many can be distracting to your viewers. Use transitions sparingly throughout your video.
- Play around to find your favorite transitions. When you find your preferred transitions, click the Star icon on a transition to add it to your Favorites for quick access.



- Use consistent transitions across your videos so viewers become familiar with what the visual transition indicates. For example, you can always use a Card Flip transition to signify switching between a desktop app to a website or a Gradient Wipe transition to convey the passage of time.
- Make sure the transition serves a purpose in the video. It should help support the message or tone of the video, not distract your viewers.

Animations In-Depth


Learn how to create and edit animations to add visual interest to your video.

Animations add interesting focal points to your video such as:


- A talking head that smoothly transitions or trades places with a screen recording.
- An image that enters the video from the left, pauses, then flies off the canvas to the right.
- Callouts that animate in various ways on the canvas to draw attention to an area in the video.
- Zooming in or out on important parts of your video to draw attention to key actions or enhance difficult to view parts within a video.

Add an Animation

1. Click the **Animations** tab.
2. Click the **Animations** subtab (Windows only).
3. Drag an Animation onto media on the timeline.




Camtasia displays the animation as an arrow on top of the media.



Edit an Animation

Animations move media in the video based on the change from one set of visual properties to another. These properties include position on the screen, rotation, scale, and opacity.

The tail and head of the animation arrow on the timeline indicate where the animation begins and ends. Adjust the visual properties at each point to set how the media displays at the start and end of the animation.



Note: For more detailed information about Zoom animations, see [Zoom in to Focus Attention](https://www.techsmith.com/learn/?post_type=tutorial&p=182337) (https://www.techsmith.com/learn/?post_type=tutorial&p=182337).


1. Place the playhead to the left of the animation arrow.
2. Click the **Properties** button.

3. Adjust the visual properties for the start of the animation. See [Animation Properties](#).
4. Move the playhead to the right of the animation arrow.
5. Adjust the visual properties for the end of the animation.
6. Drag the arrow tail to where you want the animation to start.
7. Drag the arrow head to where you want the animation to end.

Tip: Streamline animation editing with Edit All Animations mode.

With Edit All Animations mode, edits you make to a single animation are applied to all animations in the selected media. Click the Edit All Animations icon  at the top of the Properties panel to toggle this mode on and off.

Animation Properties



Property	Description
Scale	Drag the slider or enter a value to adjust the size as a percentage of the original media.
Opacity	Drag the slider or enter a percentage to adjust the transparency of the media.
Rotation	<p>Do any of the following to rotate the media around the Z, Y, or X axis:</p> <ul style="list-style-type: none">• Click and drag the spinner• Click a position on the spinner• Enter a degree value <p>Tip: To rotate media during an animation, set Rotation at the end of the animation arrow to 360° (clockwise) or -360° (counterclockwise).</p>
Position	Enter X, Y, or Z coordinate values to place the media relative to the center of the canvas.

Size	Enter pixel values to adjust the size of the media. Click the lock icon  to enable or disable the aspect ratio lock.
Skew	Drag the slider or enter a value between -10 and 10 to adjust the angle of the media. Tip: Pin the corners of your media to automatically adjust skew and integrate media with a background. See Create the Illusion of 3D Perspective (Corner Pinning) (https://www.techsmith.com/blog/tutorials/camtasia/corner-pinning/).


Easing

Easing helps media to look more natural as it moves during an animation. To change the easing:

1. Right-click (Windows) or Command+click (Mac) the animation arrow and select **Enable Easing** (Windows) or **Animation Easing** (Mac).
2. Select an Easing option:
 - o Exponential In/Out
 - o Linear (Windows) / None (Mac)
 - o Bounce
 - o Spring
 - o Auto (defaults to Exponential Easing)

Auto Animate Mode (Mac only)

Enable **Auto Animate Mode** to automatically add animations to the timeline as you move, rotate, and scale media on the canvas or adjust the media's visual properties.



Add Movement to Any Object (Motion Paths)


Learn how to make any media or object - such as videos, text, or images - swoop, glide, or arc across the screen.

Grab your audience's attention with objects that move gracefully across the screen. The Motion Path visual effect allows you to:

- Move text or callouts to the relevant areas of a screen recording.
- Trace the path of a line chart with an arrow annotation or graphic.
- Transition picture-in-picture video or other media elegantly onto or off of the screen.

Apply a Motion Path to an Object


1. Drag the object you want to move to the timeline.
2. Position the playhead where you want the movement to begin.
3. Click the **Visual Effects** tab.



4. Drag the **Motion Path** effect onto the object on the timeline.




The default path appears on the canvas with start and end motion points.




Edit the Motion Path

To edit the default motion path:

1. Click to select a start or end motion point on the canvas.



2. Drag the motion point to change where the path starts or ends.
3. Click and drag the Bezier handles to adjust the curve of the path.



4. Right-click the path and select **Add Motion Point** to add additional curves as needed.
5. To adjust the duration and timing of the motion, click and drag the motion points on the timeline.




6. Click **Finish Editing** in the Properties panel to return to normal editing mode.

Note: If you move the object on the canvas, any applied motion path will move with the object.


Motion Path Properties

When you apply a motion path to an object, motion path properties open in editing mode in the [Properties panel](https://www.techsmith.com/learn/tutorials/camtasia/media-properties/) (<https://www.techsmith.com/learn/tutorials/camtasia/media-properties/>).



Edit the properties to manually customize the object's movement along the path:

- **Line Type:** Specify the type of motion through a selected point: angle, curve, or a combination of both.
- **Easing:** Slow the media as it moves through a motion point.
- **Auto Orient:** Automatically rotate the media as it follows the path.



Click **Finish Editing** in the Properties panel to edit other properties or objects on the canvas.

Blur or Mask a Video


Learn how to add blur or shape annotations to hide portions of the video containing confidential or distracting content.

Blur an Area


Add a blur effect to cover sensitive information in a video such as names or email addresses.

Note: Viewers can decode some blurred numbers and text. We recommend using other annotations, such as callouts or shapes, to cover critically confidential information. See [Mask an Area](#).

1. Click the **Visual Effects** tab.




2. Drag the **Blur Region** effect onto the canvas or timeline over the object to hide.



Note: Blur Region is applied as an effect on the media so the blur will move and resize as the media is moved or resized.

3. Click and drag the blur shape handles on the canvas to cover the object to hide.
4. In the Properties Panel, do the following:



- Drag the **Blur** slider to adjust the amount to blur.
- Select a **Tint** color from the dropdown.
- Drag the **Opacity** slider to adjust the amount of transparency of the blur.
- Select **Oval** or **Rectangle** from the Shape dropdown.
- Click the **Invert** checkbox for a blur spotlight effect.
- Drag the **Corners** slider to adjust the corner rounding of the blur shape.
- Drag the **Feather** slider to adjust edge softness of the blur.
- Adjust the **Ease In** control to set how quickly the blur effect appears on the Canvas. When set to 0.00s, the effect appears immediately at the beginning of the media.
- Adjust the **Ease Out** control to set how quickly the blur effect disappears from the Canvas. When set to 0.00s, the effect disappears immediately at the end of the media.

▼ For Camtasia 2022.0.4 and older

1. Click the **Annotations > Blur & Highlight** tab.



2. Drag a blur annotation onto the canvas or timeline:

- **Blur**: Applies a standard blur effect.



- **Pixelate:** Applies a square or pixel blur.




- **Spotlight:** Dims the video outside the selected area.




3. Click and drag the blur annotation on the canvas over the object to hide.

- To move the blur, drag the center of the annotation to the desired location.




- To resize the blur, drag the handles in any direction.



4. To change the duration, drag an end of the blur annotation on the timeline in either direction.




5. Click **Properties** and drag the **Intensity** slider to adjust the amount to blur.



Mask an Area


Add a shape annotation to cover up a pop-up, simplify a video, or hide confidential content.




1. Click the **Annotations > Shapes** subtab.




2. Drag a shape annotation onto the canvas or timeline.
3. Click and drag the shape annotation on the canvas over the object to hide.
4. Position the shape annotation on the canvas.
 - o To move the shape, drag the center of the annotation to the desired location.



- o To resize the shape, drag the handles in any direction.



5. To change the duration, drag the end of the shape annotation on the timeline in either direction.




6. Click **Properties** to customize the shape annotation. See [Discover the Properties Panel \(https://www.techsmith.com/blog/tutorials/camtasia-2022/media-properties-2022/\)](https://www.techsmith.com/blog/tutorials/camtasia-2022/media-properties-2022/).


Blur or Mask a Moving Object

Add an animation to cover up or blur a moving object in your video.

1. Add a blur or [shape](#) annotation onto the canvas or timeline and align with the object to hide.
2. Select **Animations > Animations** subtab (Windows) or click **Animations** tab (Mac).
3. Drag the **Custom** animation onto the shape or blur annotation on the timeline.
4. Drag the arrow tail on the timeline to where the motion begins.



5. Drag the arrow head on the timeline to where the motion ends.



6. Drag the playhead to the right of the animation arrow until the red dot appears.
7. Click and drag the shape or blur on the canvas to the new location of the object to hide.

Note: For more detailed information about animations, see [Animations In-Depth](https://www.techsmith.com/learn/?post_type=tutorial&p=182340) (https://www.techsmith.com/learn/?post_type=tutorial&p=182340).

The blur or shape annotation moves with and covers the object in the video.


Animate Text & Images with Behaviors

Learn how to apply and customize Camtasia Behaviors to quickly make eye-catching videos with a unique look and feel.

Camtasia Behaviors are pre-made animations that quickly add professionalism and polish to your videos.


Add a Behavior

1. Click the **Behaviors** tab.



2. Drag a behavior animation onto media on the timeline.

Behaviors appear as an effect in the effects tray.




Note: Add multiple behaviors to the same media to create interesting animation effects.

Edit a Behavior

Customize how a behavior enters the screen, what it does when it's on the screen, and how it leaves.

1. Click to select media with a behavior applied on the timeline. If the media is in a group, expand the group before applying the behavior otherwise the entire group is affected by the behavior. See [How to Use Group Tabs \(https://www.techsmith.com/learn/?post_type=tutorial&p=182316\)](https://www.techsmith.com/learn/?post_type=tutorial&p=182316).

2. Open the **Properties** panel > **Behaviors** subtab.




3. Edit the behavior properties for the In, During, and Out tabs. For more details on each property, see [Behavior Properties](#).
4. Click the + button in the properties panel to save the customized behavior as a preset for future use (optional).

Note: Select multiple media with behaviors applied to edit the behaviors in the properties panel simultaneously.

Behavior Properties

Style and movement properties are automatically set to compatible options when a new behavior is added to the timeline. Any change to the style or movement properties will also change which properties are available to edit.



Each stage of the animation (In, During, and Out) has its own editable properties under the corresponding properties subtab.

In and Out Subtabs

Property	Description
Style	Set the type of animation for how the media enters and leaves the canvas.
Movement	Set the type of easing related to the selected animation style.

Direction (as available)	Set the direction of the media as it enters and leaves the canvas. Availability of this property depends on the selected style.
Speed/Tension (as available)	Set the pace of movement for the selected style. Availability of this property depends on the selected style.

During Subtab


Property	Description
Style	Set the type of animation while the media is visible on the canvas.
Movement	Set the type of easing related to the selected animation style.
Opacity/Jump/Rotation/Scale/Shift (as available)	Set the intensity of the related behavior. Availability of this property depends on the selected style.
Loop Time	Set the number of seconds for the behavior to finish a loop.
Delay	Set the number of seconds between each behavior loop.
Loops	Set the number of times the behavior loops. Select Loop Forever to continually repeat the behavior while the media is visible on the canvas.

Zoom In to Focus Attention

Zoom in or out on important parts of your video to draw attention to key actions or enhance difficult to view parts within a video.



Zoom-n-Pan

Quickly add zoom in, zoom out, and pan animations on the timeline.




Windows

1. Drag the playhead on the timeline to where you want the zoom to occur.
2. Select **Animations > Zoom-n-Pan subtab**.
3. Move and resize the zoom rectangle to get the desired effect. The area fills the canvas and displays what your viewers see.




4. A zoom animation appears on the timeline.



- o To position when the animation occurs, drag the arrow.



- o To change the animation duration, drag either end of the arrow.




5. To zoom out, drag the playhead where the zoom animation ends. Repeat steps 3 and 4 to zoom out or use the **Scale to fit** button to quickly zoom to full scale. A second animation arrow appears on the timeline.



Mac


1. Drag the playhead on the timeline to where you want the zoom to occur.
2. Click to select the media or group to apply the zoom and pan to.

3. Select **Edit menu > Zoom-n-Pan**. The Zoom and Pan Window appears. The highlighted area in the white rectangle is what your viewers see.



4. Complete any of the following options:


- o Resize the white rectangle to zoom in or out. Yellow lines appear when the preview snaps to the canvas edge.



- o Move the rectangle to pan across the canvas.




- Drag the **Zoom** slider or enter a percentage value to zoom in or out.



- Click **Actual size** to scale the video to 100% its original size.
- Click **Scale to fit** to display the entire media on the canvas.

5. An animation arrow appears on the timeline.

- To position when the animation occurs, drag the arrow.



- To change the animation duration, drag either end of the arrow.



6. Drag the playhead and repeat steps 4 and 5 to add more zoom and pan animations.

SmartFocus

SmartFocus™ collects data during recordings such as cursor movements, mouse clicks, and other actions and uses that to add zoom and pan animations to your media.

Note: SmartFocus can only be applied to .trec files using Camtasia version 2019 or later.

1. Select **Animations > Animations subtab**.
2. Drag the **Smart Focus** animation onto a .trec file on the timeline.

Tip: Apply SmartFocus first.

To apply additional zoom and pan animations manually, see [Manually Apply Zoom Animations](#).

To help SmartFocus predict where to apply zoom and pan animations, follow the tips below during recording:

- **Slow down.** Use slow, deliberate mouse movements.
- **Limit clicking.** Do not randomly click around the screen or repeatedly click with the mouse.
- **Record at full screen dimensions and produce at smaller dimensions.** SmartFocus is ideal for cases where you need to record at full screen or large dimensions, but want to produce the final video at smaller dimensions. For example, if you record a full screen application and then produce the final video for distribution on a smaller mobile device, the full screen recording is not clearly viewable at the original dimensions without zooming.

Note: After applying SmartFocus, a dialog appears with the option to change the editing dimensions of your video to a smaller size.

- **Record clips longer than 30 seconds.** SmartFocus is optimized for recordings longer than 30 seconds. For shorter clips, manually add zoom and pan animations. See [Manually Apply Zoom Animations](#).
- **Do not “talk” with the cursor.** Do not move the cursor around or point at unnecessary areas on the screen as you speak. Try to keep the cursor still in the area of focus in the recording unless you are demonstrating a focused action.
- **Keep the cursor close when entering text.** SmartFocus may not predict the correct action if you click in a text box, move the cursor to the other side of the screen, and then start talking. If you want the viewer to see what is typed into the text box, keep the cursor in or near the text box.
- **Use the mouse scroll wheel (if applicable).** Try using the mouse scroll wheel instead of clicking and dragging on the scroll bar. SmartFocus may zoom in on the scroll bar instead of the content scrolling. For example, use the mouse scroll wheel when scrolling long web pages.


SmartFocus at Time (Mac Only)

SmartFocus at Time allows you to apply SmartFocus at a specific point in your video.

1. Drag the playhead on the timeline to where you want to apply SmartFocus.
2. Click the **Animations** tab.
3. Drag the **SmartFocus at Time** animation onto a .trec file on the timeline.


Manually Apply Zoom Animations

Manually apply zoom animations, for example after applying SmartFocus or when recordings are longer than 30 seconds.



1. Select the **Animations tab > Animations subtab** (Windows) or click the **Animations tab** (Mac).
2. Drag the **Scale Up** animation onto media on the timeline.

- o To position when the animation occurs, drag the arrow.




- o To change the animation duration, drag either end of the arrow.



3. Click **Properties** to customize the annotation. See [Discover the Properties Panel](https://www.techsmith.com/learn/tutorials/camtasia/media-properties/) (<https://www.techsmith.com/learn/tutorials/camtasia/media-properties/>).

- o To adjust the zoom, move the playhead to the right of the arrow and drag the **Scale** slider.




4. To zoom out, drag the **Scale Down** or **Scale to Fit** animation onto the media on the timeline and adjust the location, duration, and properties of the animation.

Preview the animations on the canvas to see how they appear in the final video.

Create Stunning Animations with Media Mattes


Learn how to create stunning animations or transitions with the Media Matte effect.



About Media Mattes

The Media Matte visual effect is a simplified way to add track mattes or “masking” to your videos.

When you apply the Media Matte effect to media on a track on the timeline, sections of the media on the tracks directly below display or are hidden by transparency and brightness properties of the media on the track above.




Camtasia supports the following transparent media file formats: .mp4, .mov, .gif, .png, and .bmp.

Note: Apply a Media Matte with Alpha mode to a track that contains media with transparent pixels or media that does not cover the entire canvas such as still images and annotations.

Apply a Media Matte Effect

Apply a Media Matte effect to compatible media on a track.

1. Click the **Visual Effects** tab.
2. Drag the **Media Matte** effect onto an image or clip on the timeline.
3. Click the **Properties** button.
4. Select a mode from the Mode dropdown. See [Media Matte Modes](#).




5. Drag the **Intensity** slider to adjust the visibility of the selected mode.
6. Set the amount of time you want the effect to Ease In or Ease Out during playback. (Optional)

Note: Create complex track matte animations and transitions by grouping media. See [How to Use Group Tabs \(https://www.techsmith.com/learn/?post_type=tutorial&p=182316\)](https://www.techsmith.com/learn/?post_type=tutorial&p=182316).

Media Matte Modes


There are four modes available in the Properties panel after applying the Media Matte effect:



- **Alpha:** Media on the tracks below is not visible through the transparent pixels and visible through the opaque pixels on the track above.
 - Maximum Intensity = 100% visible
 - Minimum Intensity = 0% visible
- **Alpha Invert:** Media on the tracks below is visible through the transparent pixels and not visible through opaque pixels on the track above.
 - Maximum Intensity = 0% visible
 - Minimum Intensity = 100% visible
- **Luminosity:** Intensity of the media brightness determines the level of pixel visibility and transparency between tracks.
 - Maximum Intensity = 100% visible
 - Minimum Intensity = 0% visible
- **Luminosity Invert:** Intensity of the media brightness determines the level of pixel visibility and transparency between tracks.
 - Maximum Intensity = 0% visible
 - Minimum Intensity = 100% visible

Add Track Mattes Manually

To manually enable track mattes on the Camtasia timeline, right-click (Windows) or Control+click (Mac) the  icon on a track and select a Track Matte Mode option: **Alpha**, **Alpha Invert**, **Luminosity**, or **Luminosity Invert**. See [Media Matte Modes](#).



Additional Resources

- **Track Mattes Explained:** This [6-minute YouTube video](https://www.youtube.com/watch?v=0TDd9K4Mg2g) (<https://www.youtube.com/watch?v=0TDd9K4Mg2g>) shows the manual alternative workflow using track mattes.
- **Track Mattes Reference PDF:** Download this [reference PDF](https://www.techsmith.com/blog/wp-content/uploads/2022/02/TrackMattes_EN_2022-1.pdf) (https://www.techsmith.com/blog/wp-content/uploads/2022/02/TrackMattes_EN_2022-1.pdf) of track matte modes and timeline navigation shortcuts.
- **Track Mattes Getting Started Project:** Download this [sample project package](https://content.screencast.com/users/ScreencastViking/folders/Camtasia%202020%20Track%20Matte%20Project/5e07-42ff-9e25-6a56ff9fd2dc/TrackMatteExampleProject.campackage?downloadOnly=true) (<https://content.screencast.com/users/ScreencastViking/folders/Camtasia%202020%20Track%20Matte%20Project/5e07-42ff-9e25-6a56ff9fd2dc/TrackMatteExampleProject.campackage?downloadOnly=true>) with media, track matte, and animation to experiment on your own. See [How to Use a Template](https://www.techsmith.com/learn/?post_type=tutorial&p=182297) (https://www.techsmith.com/learn/?post_type=tutorial&p=182297) to learn how to import and create a video project from this template.

Add Dynamic Captions

Learn how to automatically transcribe audio into customizable, onscreen caption text.

Caption Types

Camtasia allows you to create and publish two common video caption types:

Closed Captions



- Viewers can turn captions on or off in the video player controls.
- Help meet video accessibility guidelines.

Dynamic Captions





- Always display onscreen as part of the video.
- Stylistic captions often used in social media videos or as a visual effect to enhance the video content or message.

Note: This tutorial covers how to add **dynamic captions** to your video. To learn how to add closed captions, see [Add Closed Captions to a Video](https://www.techsmith.com/learn/tutorials/camtasia/add-closed-captions/) (<https://www.techsmith.com/learn/tutorials/camtasia/add-closed-captions/>).

1. Generate Dynamic Captions


To generate dynamic captions based on the audio on the timeline:

1. In Camtasia Editor, select **Captions tab > Dynamic Captions subtab**.
2. From the Dynamic Caption Styles, drag a style onto a track above the audio clip on the timeline.



3. If media on the tracks below contain voice-overs, Camtasia transcribes the audio and generates dynamic captions.

To change the duration the captions appear in the video or to generate captions for other media on the timeline, drag the end of the dynamic caption on the timeline.



4. Complete the following to position the dynamic captions on the canvas:
 - To move the captions, click and drag the dynamic captions to the desired location.
 - To change size of the caption box, click and drag a white handle in or out.

2. Edit Dynamic Caption Text

To review and edit individual words in the auto-generated dynamic captions:

1. Click to select the media on the timeline. If the media contains a voice-over, the dynamic caption text

appears in the **Dynamic Caption Transcription** area on the **Dynamic Captions** subtab.

2. Complete any of the following edits:


- **Edit a Word:** Click the text box and edit the selected word.
- **Delete a Word:** Click the text box to select the word and press the **Delete** key.

Note: If you delete the Dynamic Caption Style on the timeline, Camtasia saves the edits to the caption transcription with the audio media on the timeline. If you drag another Dynamic Caption Style onto the timeline, Camtasia retains your previous caption transcription edits.


3. Edit the Word Transcription Timing

Complete the following to adjust when a word appears on the screen in Camtasia version 2024.1.0 or later:


1. Click to select the audio media on the timeline.
2. Drag the **Timeline Zoom** slider to the right until you see the individual words in the purple transcript bar.



Note: If you do not see words in the purple transcript bar, in the **Timeline Tray** dropdown, select **Transcript** or press **Ctrl+T**.




3. To change when the word appears and highlights on the screen, drag the word along the transcript bar on the media.



Note: If you see a transcript gap indicator , you cannot drag the previous word beyond this point. Camtasia automatically inserts these transcript gaps to separate the previous word from the next word in your captions.

4. Customize the Dynamic Caption Style


To customize the look and style of the dynamic captions:



1. Click to select the dynamic caption on the timeline.
2. Click the **Properties** button to open the Properties panel.
3. Customize the properties on **Text Properties** tab.
4. As you edit the properties, the canvas shows a preview of the changes in the video. You can click the  **Reset** button to restore any property to the original setting.

Tip: Save your custom style as a preset.

Click the + icon to save the custom properties as a new Dynamic Caption Style to reuse across your videos.



Add Closed Captions to a Video

Learn about the various ways to add closed captions to a video in Camtasia.

Captions display onscreen text synchronized with the voice-over and sounds in a video. Captions create videos accessible to a larger audience, including:

- Viewers who are deaf or hard of hearing.
- Viewers that cannot listen to audio in their current environment.
- Viewers who are non-native speakers by providing onscreen translations in the captions.

Caption Types

Camtasia allows you to create and publish two common video caption types:

Closed Captions



- Viewers can turn captions on or off in the video player controls.
- Help meet video accessibility guidelines.

Dynamic Captions



- Always display onscreen as part of the video.
- Stylistic captions often used in social media videos or as a visual effect to enhance the video content or message.

Note: This tutorial covers how to add **closed captions** to your video. To learn how to add dynamic captions, see [Add Dynamic Captions \(https://www.techsmith.com/learn/tutorials/camtasia/dynamic-captions/\)](https://www.techsmith.com/learn/tutorials/camtasia/dynamic-captions/).

Generate Closed Captions in Camtasia Editor


In Camtasia Editor, you can automatically generate captions based on the voice-over on the timeline.

▼ View Steps for Camtasia Windows

1. In Camtasia Editor, select **Captions tab > Closed Captions subtab**.
2. Click the  icon and select **Speech-to-Text**. The option is disabled if media on the timeline does not contain voice-over.
3. Camtasia transcribes the audio on the timeline into captions.
4. Review and edit the captions in the Caption Editor. See [Manually Add Captions \(Windows\)](#).

▼ View Steps for Camtasia Mac

1. In Camtasia Editor, select **Captions tab > Closed Captions subtab**.
2. Drag the **Captions** option onto the desired media on timeline.
3. The Captions track appears above the timeline. Click to select the first audio clip on the timeline to transcribe.



4. Click the  icon and select **Transcribe Selected Media**. The option is not available in the menu if the media selected does not contain voice-over.
5. Camtasia transcribes the audio in the selected media into captions. Repeat steps 2-4 for each audio media on the timeline.
6. Review and edit the captions in the Caption Editor. See [Manually Add Captions \(Mac\)](#).

Generate Captions in Camtasia Audiate

Camtasia Audiate automatically generates captions based on the transcription. In Camtasia Audiate, select **Sync dropdown > Captions dropdown > Default Captions > Sync button** to sync your Audiate edits and send captions back to your Camtasia Editor project.




See [Speed Up Editing with Audiate \(https://www.techsmith.com/learn/tutorials/camtasia/camtasia-audio-sync/\)](https://www.techsmith.com/learn/tutorials/camtasia/camtasia-audio-sync/).

Sync Captions with a Script (Windows Only)


Paste a prepared script into the caption editor and synchronize the script with the audio playback.

▼ View Steps

1. In Camtasia Editor, move the playhead to the beginning of the timeline.
2. Select **Captions tab > Closed Captions subtab**.
3. Click the **Add Caption** button.
4. Paste the full script into the caption editor.
5. Click the gear icon and select **Sync captions**.



6. Read the instructions that appear and when ready to sync captions, click **Continue**. The video begins playing and the sync controls appear below the caption editor.
7. To add a new caption, click a word when you hear the word played back.




8. Click **Pause** to pause the video playback.
9. Click **Stop** to finish syncing the script and captions.

Manually Add and Edit Captions


Manually enter or edit captions as you play back your video.

▼ Windows

1. In Camtasia Editor, select **Captions tab > Closed Captions subtab**.
2. Click the **Add Caption** button.
3. Press **Enter** to play the audio section or click the  button to loop the playback.
4. In the caption editor, type what you hear or paste the corresponding text from a written script.
 - If your caption exceeds three lines, the text changes to gray. Click the **Split** button to move the gray text into a new caption.




- o To change the duration of a caption, drag the **Duration** slider. The default duration is four seconds.



5. Click the **Add New Caption** button or press the **Tab** key to enter the caption text for the next audio section.




6. To customize the look of the closed caption text (optional), click the **Font Properties** dropdown in the caption editor and adjust the desired settings.




▼ Mac

1. In Camtasia Editor, select **Captions tab > Closed Captions subtab**.
2. Drag the **Captions** option onto a recording or media with audio on the timeline.
3. The Captions track appears above the timeline. Press **Enter** to play the audio section or click the  button to loop the playback.




4. In the caption editor, type what you hear or paste the corresponding text from a written script.



5. Click the **Next Caption** button or press the **Tab** key to enter the caption text for the next audio section. You can also click to select a specific caption section on the Captions track.

6. Complete any of the following optional edits:

- o To change the duration of a caption, drag the **Duration** slider. The default duration is four seconds.



- o If your caption is too long, Command+click on a caption segment and select **Split** to move the text into a new caption.
- o To customize the look of the caption, click the  icon and select **Caption Settings**.
- o To merge two captions, control+click the caption and select **Merge with Next Caption**.

Import or Export a Caption File

You can import or export captions as SAMI or SRT (SupRip) files. Export a caption file to upload with the video on a hosting site, for translation, or to use across platforms.

Import a Caption File

Select **File > Import > Captions** and select a SAMI or SRT file. The caption file opens in the caption editor.

Export a Caption File

1. Select the **Export menu > Export Captions**.
2. Enter a file name and select SAMI or SRT.
3. Click **Save** (Windows) or **Export** (Mac).

Export a Video with Captions

The caption type is selected during the video export process.

Export Closed Captions

Captions are turned on/off by the viewer via a CC button on the video controller.



▼ Windows

Complete one of the following options:

- Select **Export > YouTube**.
- Select **Export > Screencast**.
- Select **Export > Local File**. Select the **MP4 with Smart Player** option from the **File type** dropdown.

▼ Mac

Complete one of the following options:

- Select **Export > YouTube**.
- Select **Export > Screencast**.
- Select **Export > Local File > Export to MP4**. Enable the **Export as Web Page** option. In the **Caption Style** dropdown, select the **Closed Captions** option.

Export Burned In Captions

Also known as “open,” captions are always visible and cannot be turned off by the viewer.



▼ Windows

1. Select **Export > Local File**.
 2. In the **File type** dropdown, select **MP4 (recommended)**.
 3. Click the **Advanced Settings** dropdown arrow to access additional properties.
 4. On the Captions tab, enable the **Render video with open (always visible) captions** option.
 5. Click **Export**.
-

▼ Mac

1. Select **Export > Local File**.
 2. In the export dialog, enter a filename and select the preferred location and file format.
 3. In the **Caption Style** dropdown, select **Burned in captions**.
 4. Click **Export**.
-

Build Quizzes & Surveys

Gather feedback and learn more about your viewers by using Camtasia quizzes and surveys. Learn how to set up, edit and publish a quiz.

Insert a quiz or survey into your video to:

- Test viewer's knowledge through multiple choice, fill in the blank, short answer, and true/false questions.
- Add open ended questions to gain feedback or gather user information such as an email address to contact the viewer at a later time.

Note: The TechSmith Smart Player is required for table of contents, closed captions, search, quizzing, and hotspots in a video. To include the TechSmith Smart Player, export the video to Local File or Screencast. See [Export & Share Your Video \(https://www.techsmith.com/learn/?post_type=tutorial&p=182298\)](https://www.techsmith.com/learn/?post_type=tutorial&p=182298).

Quiz Features


- Unlimited number of fill in the blank, multiple choice, short answer, or true/false questions.
- Provide up to thirty answer options per question.
- Set the quiz to be scored or unscored.
- For surveys, use the unscored option.

Set Up a Quiz


1. Select media or move the playhead to the desired location and select **Modify > Quizzes > Add Timeline Quiz** or press **Shift+Q**.

Note: Add a quiz to media to keep the quiz aligned to that media while editing.


2. Camtasia adds the quiz and enables quiz mode.



3. Set quiz options in the **Properties > Options** tab.




4. Enter quiz questions in the **Properties > Questions** tab.





5. To add another quiz, move the cursor along the timeline or on the selected media and click to add a quiz. As long as quiz mode is enabled, you are able to add new quizzes.


6. To disable quiz mode, click the small arrow next to **Quiz** under the timeline toolbar or press **Ctrl+Q**.



Quiz Questions and Options

Option	Description
Create questions	<p>Click the Questions subtab.</p>  <ul style="list-style-type: none">• The first question is added for you.• To add more questions, click the Add Question button and type the question.

<p>Choose a question type</p>	<p>Select a question type from the dropdown.</p> 
<p>Enter or select answer</p>	<ul style="list-style-type: none"> • For true/false questions, click True or False to set the answers. • For all other question types, click Add Answer and type an answer. • For multiple choice questions, click to select the correct answer.
<p>Give feedback for answers</p>	<p>Check the Display Feedback option.</p>  <ul style="list-style-type: none"> • Type a response for the correct / incorrect answers. • Select the next action after the correct / incorrect answers.
<p>Change question order</p>	<p>Click up and down arrows to change order of the questions in the quiz.</p>

Preview how quiz appears to your viewers	<p>Click the Preview button.</p> 
Enter quiz name	<p>Click the Quiz Options subtab.</p>  <p>Enter the name in the Quiz Name field.</p>
Create survey	<p>Click the Quiz Options subtab.</p>  <p>Leave the Score Quiz option unchecked.</p>
Allow users to view results	<p>Click the Quiz Options subtab.</p>  <p>Click the Viewers can see their results checkbox.</p>
Delete quiz	<p>Select a quiz on the timeline or media and press the Delete key.</p>
Get scores and information about quiz	<p>You can report the results of the quiz via a SCORM-compliant Learning Management System (LMS).</p>

Export a Video with a Quiz

To export a video with a quiz, select one of the following options:

- **Local File (Windows):**

1. Select **Export > Local File**.
2. Select the **MP4 with Smart Player** option from the **File type** dropdown.
3. Optional: If you want to upload the video package to a SCORM compliant LMS, select **Advanced > Smart Player** tab > enable the **Report using SCORM** option. Click the **SCORM options** button to customize.
4. Click **Export**.

- **Local File (Mac):**

1. Select **Export > Local File**.
2. Select **Export to MP4** from the **File format** dropdown.
3. Enable the **Include Quiz** option. Click the **Options** button.

4. Optional: If you want to upload the video package to a SCORM compliant LMS, enable the **Include SCORM** option. Click the **Options** button to customize.

5. Click **Export**.

- **Screencast:**

1. Select **Export > Screencast**.

2. Enter a title and optional video description.

3. Click **Export** (on Windows) or **Share** (on Mac).

Add Hotspots (Interactive Videos)

Learn how to link to a webpage, automatically pause your video, or direct users to replay or jump to different sections with Camtasia's interactive hotspots.

Hotspots provide a clickable call-to-action in a video such as:

- Open the next video in a series.
- Provide a link to subscribe to your newsletter, channel, or social media.
- Jump to a specific point in a video to learn more based on the viewer's interest.
- Provide a link to purchase your product or software.

Add a Hotspot

1. Click the **Visual Effects** tab.
2. Drag the **Interactive Hotspot** effect onto the visual media on the timeline you want to use as the call-to-action, such as text, image, or annotation.
3. Click the **Properties** button to customize the hotspot. The default pauses the video at the end of a hotspot and requires the user to click to continue. Other options include:
 - **URL:** Send the viewer to the URL entered.
 - **Marker:** Send the viewer to a specific marker in the video. You must have markers on the timeline to select this option. See [Add Markers & Video Table of Contents \(https://www.techsmith.com/learn/?post_type=tutorial&p=182313\)](https://www.techsmith.com/learn/?post_type=tutorial&p=182313).
 - **Time:** Send the viewer to a specific time or frame in the video.
4. To test the URL, Marker, or Time Options, click the **Test** button.

Note: The TechSmith Smart Player is required for table of contents, closed captions, search, quizzing, and hotspots in a video. To include the TechSmith Smart Player, export the video to Local File (MP4 with Smart Player) or Screencast. See [Export & Share Your Video \(https://www.techsmith.com/learn/?post_type=tutorial&p=182298\)](https://www.techsmith.com/learn/?post_type=tutorial&p=182298).

Introduction to Cursor Editing

Learn how to complete basic cursor edits to add emphasis or support your video message.

Camtasia records the screen and cursor data separately in the Camtasia Recording file format (TREC). This allows you to edit the cursor and eliminates the need to rerecord to perfect cursor movement or position.

Camtasia's cursor editing and effects help to:

- Smooth jumpy cursor movements.
- Fix the cursor position when it doesn't match the narration.
- Emphasize the cursor to support the message in your videos.
- Add or edit cursor clicks.

Basic Cursor Edits


- [Change the Cursor Size \(Scale\)](#)
- [Replace the Cursor](#)
- [Hide the Cursor](#)
- [Add Cursor Effects](#)
- [Add or Edit Cursor Clicks](#)
- [Edit the Cursor Path](#)
- [Design a New Cursor Path](#)

Change the Cursor Size (Scale)

Increase the scale to emphasize the cursor and help your viewers follow along with the video.

▼ Learn How

1. Click to select a TREC recording on the timeline.
2. Click the **Properties** button.
3. On the Cursor Properties tab, drag the **Scale** slider to change the cursor size.



Replace the Cursor

The cursor shown on the screen changes as you interact with different areas on the screen. In Camtasia recordings (TREC), you can replace the cursor type to use a consistent cursor throughout your entire recording or replace the cursor with a custom image. See [Replace the Cursor \(https://www.techsmith.com/learn/tutorials/camtasia/change-cursor/\)](https://www.techsmith.com/learn/tutorials/camtasia/change-cursor/).

Hide the Cursor


You can hide the cursor on any Camtasia Recording file (TREC) added to the timeline. Consider hiding the cursor for sections where the cursor does not provide additional value or if it distracts from the action on the screen.

▼ For the Entire Clip


1. Click to select a TREC recording on the timeline.
2. Click the **Properties** button.
3. In the Properties panel, select the **Cursor Properties** tab.
4. Set the **Opacity** to 0%.

▼ For a Section in the Recording – Set to No Cursor Image


1. Click to select a TREC recording on the timeline.
2. Click the **Properties** button.
3. In the Properties panel, select the **Cursor Properties** tab.
4. The cursor images appear on the selected TREC file on the timeline.




Drag the playhead to the cursor image to replace. Drag the **Zoom** slider to the right to zoom in on the timeline to make it easier to view the cursor image keyframes.



5. On the **Cursor Properties** tab, click the **Cursor** dropdown.




6. The Replace Cursor Image options appear. Select **Current** to replace the cursor at the playhead location on the timeline.
7. Select the **No Cursor** option for the cursor image type.




Camtasia hides the cursor until the next cursor keyframe appears in the TREC recording.

▼ For a Section in the Recording – Change the Cursor Opacity to 0%


1. Select **Animations tab > Animations subtab**.




2. Drag the **Custom** animation onto the TREC on the timeline.
3. Drag the animation arrow to the location to start hiding the cursor.




4. In the properties, click the **Cursor** tab and set the **Opacity** to 0%.



5. To show the cursor again in the video, drag another **Custom** animation onto the TREC on the timeline.
6. Drag the end of the animation arrow to the location for the cursor to appear.



7. In the properties, click the **Cursor** tab and set the **Opacity** to 100%.



Add Cursor Effects

Add a cursor effect to a Camtasia Recording file (TREC) on the timeline to emphasize the cursor to support the message in your videos. See [Add Cursor Effects. \(https://www.techsmith.com/learn/tutorials/camtasia/cursor-effects/\)](https://www.techsmith.com/learn/tutorials/camtasia/cursor-effects/)

Add or Edit Cursor Clicks

In the Camtasia Recording file (TREC), you can add or edit mouse clicks at any time. Apply a cursor click effect to visually emphasize a click. You can also add new cursor keyframes to simulate a click in an image, video, or recording file. See [Add a Click Effect & Edit Cursor Clicks](https://www.techsmith.com/learn/tutorials/camtasia/cursor-effects/#h-add-a-click-effect-amp-edit-cursor-clicks) (<https://www.techsmith.com/learn/tutorials/camtasia/cursor-effects/#h-add-a-click-effect-amp-edit-cursor-clicks>).

Edit the Cursor Path

In Camtasia Recording files (TREC), you can fix the cursor position when it doesn't match the narration or smooth out cursor movements post-recording. See [Customize Your Cursor and Path](https://www.techsmith.com/learn/?post_type=tutorial&p=236752) (https://www.techsmith.com/learn/?post_type=tutorial&p=236752).

Design a New Cursor Path

No need for the perfect recording! You can design your own cursor path and add cursor clicks to simulate cursor movement on any image, video, or TREC recording file. See [Customize Your Cursor and Path](https://www.techsmith.com/learn/?post_type=tutorial&p=236752) (https://www.techsmith.com/learn/?post_type=tutorial&p=236752).

Add Cursor Effects

Learn how to add cursor effects to emphasize the cursor and edit cursor clicks.

Introduction

Most videos have the cursor burned into the recording file. Camtasia records the screen and cursor data separately in the Camtasia Recording file format (TREC). This allows you to edit the cursor and eliminates the need to rerecord to perfect cursor movement or position.

Camtasia's cursor editing and effects help to:


- Smooth jumpy cursor movements.
- Fix the cursor position when it doesn't match the narration.
- Emphasize the cursor to support the message in your videos.
- Add or edit cursor clicks.

If you want to add a cursor to a still image or a video not recorded in Camtasia, you can add the **Cursor Path Creator** effect to design the cursor path. Add a **Left Click** or **Right Click** effect to add cursor click keyframes to simulate clicks. See [Add a Click Effect & Edit Cursor Clicks](#).


Add a Cursor Effect

Add a cursor effect to a Camtasia Recording file (TREC) on the timeline to emphasize the cursor to support the message in your videos.


1. Select **Cursor Effects tab > Cursor Effects subtab**.



2. Drag an effect onto the Camtasia Recording file (TREC) on the timeline. See [Cursor Effect Types](#).
3. Click the arrow to open the Effects tray.



4. By default, the effect is applied to the entire duration of the media. To adjust the duration, click to select the effect and drag the ends to adjust when the effect starts and ends during the clip.




5. In the Properties panel, customize the properties available for the effect.

Add a Click Effect & Edit Cursor Clicks


In the Camtasia Recording file format (TREC), you can add or edit mouse clicks at any time. Apply a cursor click effect to visually emphasize a click. You can also add new cursor keyframes to simulate a click in an image, video, or recording file.

▼ For Camtasia Recordings (TREC Files)


1. Select **Cursor Effects** tab > **Left Click** or **Right Click** subtab.




2. Drag an effect onto the Camtasia Recording file (TREC) on the timeline. See [Cursor Effect Types](#).
3. Click the arrow to open the Effects tray.



4. By default, the effect is applied to the entire duration of the media. To adjust the duration, click to select the effect and drag the ends to adjust when the effect starts and ends during the clip.




5. In the Properties panel, customize the properties available for the effect.
6. The circles on the effect show where clicks occur in the media. Click the **Previous** and **Next** buttons to navigate through the cursor clicks.
 - To add a new cursor click, drag the playhead on the timeline to the desired location and click the **Cursor Keyframe** button in the properties.




- To remove a cursor click, click the **Previous** and **Next** buttons to navigate to the desired cursor click and click the **Cursor Keyframe** button to remove the selected click.

▼ For Images or Videos Created in Other Applications


1. Click the **Cursor Effects** tab.
2. On the **Cursor Effects** subtab, drag the **Cursor Path Creator** effect onto media on the timeline and set up the cursor path. See [Customize Your Cursor and Path \(https://www.techsmith.com/learn/tutorials/camtasia/customize-your-cursor-path-2/\)](https://www.techsmith.com/learn/tutorials/camtasia/customize-your-cursor-path-2/).
3. Select **Cursor Effects tab > Left Click or Right Click subtab**.




4. Drag an effect onto the media on the timeline. See [Cursor Effect Types](#).
5. Click the arrow to open the Effects tray.



6. By default, the effect is applied to the entire duration of the media. To adjust the duration, click to select the effect and drag the ends to adjust when the effect starts and ends during the clip.



7. In the Properties panel, customize the properties available for the effect.
8. To add a new cursor click, drag the playhead on the timeline to the desired location and click the **Cursor Keyframe** button in the properties.
9. The circles on the effect show where clicks occur in the media. To remove a cursor click, click the **Previous** and **Next** buttons to navigate to the desired cursor click and click the **Cursor Keyframe** button to remove the selected click.



Cursor Effect Types

General Cursor Effects

Cursor Color

Edit the cursor fill and outline colors to match the video aesthetic or to stand out from the screen content.

Cursor Highlight

Add a circle of color to draw viewers' attention to the cursor.

Cursor Path Creator

Add to images or videos recorded outside of Camtasia to design your own cursor path to simulate a demo or recording. Combine with left or right click effects to build click actions on anything! See [Customize Your Cursor and Path](https://www.techsmith.com/learn/?post_type=tutorial&p=236752) (https://www.techsmith.com/learn/?post_type=tutorial&p=236752).

Cursor Smoothing

Transform distracting, jumpy cursor movements into smooth lines. See [Quickly Smooth Cursor Movements](https://www.techsmith.com/learn/?post_type=tutorial&p=182331) (https://www.techsmith.com/learn/?post_type=tutorial&p=182331).

Cursor Glow

Emphasize the cursor with a glow effect. Give your cursor a glow effect to stand out on the screen and grab viewers' attention.

Cursor Magnify

Enlarge the cursor area to show detail.

Cursor Shadow

Add a visual effect that makes your cursor appear to float above the screen.

Cursor Spotlight

Dim and blur the area outside of the highlighted cursor area to emphasize specific actions and cursor movements.

Left Click & Right Click Effects

Click effects help to visually emphasize the action of a click within a video.

Rings

Add an expanding ring over the mouse click area.

Scaling

Add for the perfect visual indicator for a mouse click.

Sound

Combine with other click effects to emphasize a cursor click.

Warp

Add a transparent visual effect to emphasize the mouse click that appears to push in the area around the mouse click.

Ripple

Add a transparent ripple over the mouse click area.

Scope

Add a visual target over the mouse click area.

Target

Add a circular visual target over the mouse click area.

Tip: Combine the Sound and the Scaling click effects to emphasize a click.

You can add multiple cursor effects to a clip. These two click effects pair perfectly together to emphasize the action of a click.

Replace the Cursor

Learn how to replace the cursor image in TREC recording files.

After recording, you can change the cursor in any Camtasia recording file (TREC). Change the cursor to:

- Maintain a consistent cursor throughout your entire recording to reduce visual distractions.
- Emphasize cursor movement with a custom cursor.
- Match the operating system cursors when creating recordings for multiple platforms.
- Replace the cursor with any of Camtasia's professionally-designed cursors for a fun theme or to add emphasis.


Replace the Current Cursor

Note: You can only change or edit the cursor in the Camtasia Recording file format (TREC). For videos recorded outside of Camtasia, the cursor is burned into the recording file and cannot be edited.


1. Click to select a Camtasia Recording file (TREC) on the timeline.
2. Click the **Properties** button.
3. In the Properties panel, select the **Cursor Properties** tab.




4. The cursor images appear on the selected TREC file on the timeline.



Drag the playhead to the cursor image to replace. Drag the **Zoom** slider to the right to zoom in on the timeline to make it easier to view the cursor images.




5. On the **Cursor Properties** tab, click the **Cursor** dropdown.



6. Select one of the following options:


- **Current:** Replace only the current cursor at the playhead.
- **Similar:** Replace all cursors in the selected TREC file for this cursor type.
- **All:** Replace all cursors in the selected TREC file.

7. Select a cursor type from the dropdown and then select the desired cursor.



Tip: Hide the Cursor for a Section in the Recording.

Select the **No Cursor** option as the cursor image to hide the cursor for part of the recording.




Add a Custom Cursor

You can import and image file to use as a custom cursor.


1. Click to select a Camtasia Recording file (TREC) on the timeline.
2. Click the **Properties** button.
3. In the Properties panel, select the **Cursor Properties** tab.




4. On the **Cursor Properties** tab, click the **Cursor** dropdown.



5. Click the **Import** button to add a custom cursor.



6. The Open dialog appears. Select a BMP, JPEG, PNG, or TIF image file format to use as the custom cursor image and click **Open**.
7. Edit the custom cursor properties and click the **Save Cursor Edits** button. Camtasia adds the imported cursor to the list of Custom Cursors. Follow the steps for [Replace the Current Cursor](#) to use the custom cursor in a TREC recording.



Customize the Cursor Path

Learn how to replace or import a cursor, edit a cursor path, or add a new path to your video.

Camtasia records the screen and cursor data separately in the Camtasia Recording file format (TREC). This allows you to edit the cursor and eliminates the need to rerecord to perfect cursor movement or position.

Camtasia's cursor editing and effects help to:

- Smooth jumpy cursor movements.
- Fix the cursor position when it doesn't match the narration.
- Emphasize the cursor to support the message in your videos.
- Add or edit cursor clicks.


Edit a Recorded Cursor Path

In Camtasia Recording files (TREC), you can fix the cursor position when it doesn't match the narration or smooth out cursor movements post-recording.


1. Select a Camtasia recording (TREC) on the timeline or canvas.

Note: You can only edit the cursor path on screen recordings captured with Camtasia (TREC) or after a new cursor path is added. To create a new cursor path in a video or image imported into Camtasia, see [Create a New Cursor Path](#).

2. On the cursor tab in the Properties panel, click the **Edit Cursor Path** button.



3. In the Edit Cursor Path dialog, select **Simplify Existing Path** or **Create New Path** in the dropdown and click **Continue**.



Note: You only need to complete this step the first time that you edit the cursor path.


4. The cursor path and points appear on the canvas and timeline.



5. Click to select a point to edit, then complete any of the following options:
 - o Right-click a point on the timeline and select **Delete** to remove that point.
 - o Click and drag a point on the canvas to adjust where the cursor moves in the recording.



- o Click and drag a point on the timeline to extend or reduce the duration of the cursor movement to that point. To extend the duration, drag the point to the right. To reduce the duration, drag the point to the left.




- o Select a **Line Type** in the Properties panel to set straight or curved cursor movements in and out of the point.



Note: After selecting a line type, click and drag the handle of the point on the canvas to manually adjust the curve of the cursor movement if desired.

- o Select an option from the **Easing** dropdown to set the cursor speed as it passes through the selected point for a more natural look.




6. Click and drag the playhead on the timeline to the location to edit. Right-click the playhead line, then select one of the following options to edit the cursor path:

- o **Add Cursor Point at Playhead:** Adds another point to the path to allow for more detailed control over the cursor movement and look.
- o **Split Cursor Path at Playhead:** Adds a new path segment and two new points to the timeline. This is useful if you want the cursor to pause at a location before continuing on its path.
- o **Extend Cursor Path to Playhead:** Extends the path duration to the selected location and adds two new cursor points on the timeline.

Note: The **Extend Cursor Path to Playhead** menu option is only available if the playhead is on a cursor keyframe and there is no timeline cursor path in that location.

7. If you have split cursor paths after editing, click the **Smooth cursor across edits** checkbox in the Properties panel to improve the cursor flow.
8. Click and drag the **Scale** control to adjust the size of the cursor on the canvas.
9. Click **Finish Editing** to exit cursor path editing.




Create a New Cursor Path

No need for the perfect recording! You can design your own cursor path and add cursor clicks to simulate cursor movement on any image, video, or TREC recording file.

Note: You cannot add the **Cursor Path Creator** effect to media recorded with Camtasia. To edit a cursor path in a Camtasia recording (TREC), see [Edit a Recorded Cursor Path](#).

1. Drag the **Cursor Path Creator** effect from the Cursor Effects or Visual Effects tab on to an image or video on the canvas or timeline.



2. The cursor path and points appear on the canvas and timeline. Click to select a point to edit, then complete any of the following options:
 - o Right-click a point on the timeline and select **Delete** to remove that point.


- o Click and drag a point on the canvas to adjust where the cursor moves in the recording.



- o Click and drag a point on the timeline to extend or reduce the duration of the cursor movement to that point. To extend the duration, drag the point to the right. To reduce the duration, drag the point to the left.




- o Select a **Line Type** in the Properties panel to set straight or curved cursor movements in and out of the point.



Note: After selecting a line type, click and drag the handle of the point on the canvas to manually adjust the curve of the cursor movement if desired.

- o Select an option from the **Easing** dropdown to set the cursor speed as it passes through the selected point for a more natural look.



3. Click and drag the playhead on the timeline to the location to edit. Right-click the playhead line, then select one of the following options to edit the cursor path:

- o **Add Cursor Point at Playhead:** Adds another point to the cursor path to allow for more detailed control over the cursor movement and easing of the cursor path.
- o **Split Cursor Path at Playhead:** Adds a new path segment and two new cursor points to the timeline. This is useful if you want the cursor to pause at a location before continuing on it's path.
- o **Extend Cursor Path to Playhead:** Extends the path duration to the selected location and adds two new cursor points on the timeline.


Note: The **Extend Cursor Path to Playhead** is only available if the playhead is on a cursor keyframe and there is no timeline cursor path in that location.

4. If you have split cursor paths after editing, click the **Smooth cursor across edits** checkbox in the Properties panel to improve the cursor flow.
5. Click and drag the **Scale** control to adjust the size of the cursor on the canvas.
6. Click **Finish Editing** to exit cursor path editing.



Restore the Original Cursor Path

To restore the original cursor path, click **Restore Path** in the Properties panel.



Watermark Your Videos (Windows)

Learn how to add a watermark to deter unauthorized use of your video, maintain copyright, or add a logo.


A watermark is a logo, image, or text, often transparent and superimposed over digital media. Apply a watermark to:

- Protect proprietary content.
- Brand videos on your channel or across a video series.
- Mark drafts to prevent low fidelity content from being shared or reused without permission.


Add a Watermark

On Windows, you can add a watermark when you export your video to a local file:

1. Select **Export > Local file**.
2. In the Export Local File dialog, select **Include watermark** and click **Options**.



3. In the Watermark Options dialog, click the  folder icon.
4. Browse and select an image file (BMP, JPG, JPEG, or PNG) and click **Open**.
5. The Watermark Preview shows how your video will look with the current settings.



6. Drag a slider or enter a percentage value to adjust any of the following (see [Watermark Tips](#)):

- **Scale:** Enlarge or reduce the watermark size.
- **Opacity:** Increase or reduce the watermark transparency.
- **X Offset:** Adjust the horizontal position of the watermark.
- **Y Offset:** Adjust the vertical position of the watermark.


7. After editing the desired watermark settings, click **OK**.

8. Select the file name, save location, and any other export settings, and click **Export**.

For additional details about exporting to a local file, see [Export & Share Your Video](https://www.techsmith.com/learn/tutorials/camtasia/export-share/) (<https://www.techsmith.com/learn/tutorials/camtasia/export-share/>).

Watermark Tips

- Use an image file of any of the following as a watermark:
 - Company logo



- o Channel or series logo




- o Copyright statement



- o Website address or text

- For logos or graphics with rounded corners or transparent areas, select an image file format that supports transparency (BMP or PNG).
- Prevent or deter cropping and editing around the watermark. Use text and diagonal lines or a pattern to cover the entire image.
- In the Watermark Options dialog, adjust the settings for the purpose of the watermark:
 - **To deter unauthorized sharing or reuse:** Adjust scale to cover the entire video. Decrease opacity to ensure users can still view the video through the watermark.



- **To add a watermark as a brand logo:** Set opacity to 100% to maintain the original colors. Adjust the scale, x offset, and y offset to position the logo in a corner of the video where it does not block content.

Note: Videos exported in the free trial period or in limited access mode automatically include a TechSmith watermark. You must purchase Camtasia to export videos without this watermark.




Batch Export Videos

Learn how to export multiple videos based on presets.

Overview

The Batch Exporter helps you to:

- Quickly export a series of videos from a Camtasia project or video file to repurpose the content to fit various platforms, video styles, or quality requirements.
- Export a video file or project into multiple formats.
- Maintain productivity by running the export process in the background while you create or edit another project.
- Quickly edit the output location across your batch files to improve file management.




Add Projects to the Batch Export Queue (Windows)


In Camtasia Windows, you can add Camtasia projects (.tscproj) or video files (.trec and .mp4) to a queue and export multiple files based on the selected export preset for each.

1. Open Camtasia.
2. In the Home hub, open a recent project or select **New Project**.
3. Camtasia Editor opens. Select **Export > Batch Export**.
4. The Batch Exporter dialog opens. Click the **Add Files / Projects** button to select a project to add to the export queue.

- Browse to find Camtasia Projects (.tscproj), .trec, or .mp4 files to add.
- Click the **Open** button to add the project to the queue.
- For each project in the queue, select an export preset from the **Preset** dropdown menu. To create custom export presets, see [Set up Export Presets](#).



Note: If your project contains [markers](https://www.techsmith.com/learn/tutorials/camtasia/markers-and-table-of-contents/) (<https://www.techsmith.com/learn/tutorials/camtasia/markers-and-table-of-contents/>), you can export multiple videos based on the markers in the project in Camtasia version 2023.4.2 or later. Click the dropdown next to the project name, and select the **Create multiple files from markers** checkbox.



- To change the export location, click the **Output Location** path, browse to select a new file location, and click **Select Folder**.
- Click the **Start Export** button.

You can continue to work in Camtasia Editor and open other projects while the batch exporter is running.

Status Column


The Batch Exporter indicates the status of each project in the queue.

Status	Description / Action to Take
Ready	<p>The project is ready for batch export.</p> <ul style="list-style-type: none">• Click the Start Export button to export the projects in the queue.• To remove a project from the queue, right-click the project name and select Remove.
Error	<p>There was an error in the project and the file cannot be included in the batch export. Hover your cursor over the Error status for more information.</p>
Warning	<p>Hover your cursor over the Warning status for more information.</p>
Progress bar	<p>A progress bar appears in the Status column when Camtasia has started exporting the selected project.</p> <p>To cancel export for all files in the queue, click the Cancel All button.</p>
Finished	<p>The export for this project is complete.</p> <p>Right-click the project name and select Open Exported File Location to view the exported file. The file location is also listed in the Output Location column.</p>
Canceled	<p>The export was not completed.</p>

Set up Export Presets (Windows only)

Create a preset to save your custom export settings. Presets save time and are great for quickly applying specific export preferences based on platform, video type, or quality.


1. In Camtasia, open a recent project.
2. Select **Export > Local File**.
3. The Export Local File dialog appears. Click to expand the **Advanced Settings**.




4. Customize the desired settings on the **Dimensions**, **Encoding**, and **Audio** tabs.
5. Click the  button to add a new preset.
6. The Add Exporter Preset dialog appears. Enter a name and click **OK**.

Camtasia saves the Windows export preset. You can select and apply this preset in the following preset dropdown locations:

- Select **Export > Local File > Advanced Settings > Presets dropdown**.



- Select **Export > Batch Export > Presets dropdown**.



Batch Export Multiple Projects to a Single Export Type (Mac)

In Camtasia Mac, you can add multiple projects to the batch export queue to export multiple files based on the same file type or export settings.

1. Open Camtasia.
2. Select **Export > Batch Export** button.

3. The Batch Export dialog opens. Click the **Add Project** button.
4. Browse to find Camtasia Project (.cmproj) files to add. Shift+click to add multiple .cmproj files.
5. Click the **Select Project(s)** button to add the project to the queue.
6. To change the export location, click the **Select** button, browse to select a new file location and click **Select**.
7. To customize the batch export settings for the projects in the queue, select a file format from the dropdown and click the **Options** button to edit the export settings.
8. Click the **Start** button.

Export an Audio File

Learn how to export a standalone audio file from your Camtasia project.

Export audio from your project as a standalone .mp3, .m4a, or .wav audio file.

Note: The exported audio file includes all enabled audio tracks. To export the audio from only one track on the timeline, hold the **Alt** key (Windows) or **Option** key (Mac) and click the  icon to the left of the track. The icon changes to  and all other tracks are disabled and not included in the exported file.

1. Select **Export** menu > **Export Audio Only**.
2. Enter a file name and location.
3. Select a file type.
4. Click **Save** (Windows) or **Export** (Mac).


Customize Camtasia (Favorites, Presets, & More)

Learn how to personalize Camtasia to save time and add your frequently-used video enhancements and custom properties.

Save a Preset

Save custom properties for annotations, behaviors, visual effects, cursor effects, and dynamic caption styles.

1. Drag an annotation, behavior, visual effect, cursor effect, or dynamic caption style onto the timeline.
2. In the Properties panel, edit the properties to customize.




3. Click the  button to save the custom properties as a new preset.
4. The Add Preset dialog appears. Enter a Preset Name and click **OK**.

Note: Customizing the preset name is not available for annotations.

Camtasia saves the preset to the Annotations, Behaviors, Visual Effects, Cursor Effects, or Dynamic Captions tab. User-saved presets are indicated with the  icon (Windows only).

Note: To view preset annotations (callouts, arrows, shapes, etc.), select **Annotations tab > a subtab > Style dropdown > User**.



Add Your Favorites


Add frequently-used annotations, transitions, visual effects, behaviors, animations, cursor effects, and audio effects to the **Favorites** tab.

Package (<https://www.techsmith.com/learn/tutorials/camtasia/package-share-camtasia-resources/>) your Favorites to share with others to:

- Maintain a consistent look and elements across videos.
- Help your team build professional videos based on your favorite video enhancements.
- Save time by having ready-made enhancements easily accessible.

To add to Favorites:

1. Click to select the desired tool.
2. Hover over the item to add and click the  **Favorites** icon. Camtasia adds the item to the **Favorites** tab.



To remove an item from the **Favorites** tab, click the  icon.

Customize the Editor Tool Order

Quickly move your frequently-used tools to the top in Camtasia Editor.


Click and drag a tool to reposition it within the list of tools.

Tip: Detach the timeline to quickly reorder the entire set of tools.

Tools in the **More** menu cannot be reordered. To reorder the entire set of tools, select **View > Timeline > Detach Timeline** press **Ctrl+3** (Windows) or **Command+3** (Mac).

Set the Default Editor Tool

Camtasia sets the default tool to the **Automatic** option, which opens the Media Bin or Camtasia Assets subtab when you open or start a new project.



To change the default startup tool:


- On Windows, select **Camtasia Editor > Edit menu > Preferences > Program tab > Default tool dropdown**.
- On Mac, select **Camtasia Editor > Camtasia menu > Settings > General tab > Default tool dropdown**.

Add Color Labels to Media on Timeline

Assign color labels to media on the timeline to help identify media types or sections while editing.



Right-click (Windows) or control-click (Mac) on the media and select **Add Color Label**. Choose the desired color.



Restore Camtasia Defaults

Reset default annotations, visual effects, behaviors, cursor effects, audio effects, and dynamic caption styles in the selected tab to the original defaults.

1. Click to select one of the Tool tabs.
2. Right-click (Windows) or Control+click (Mac) in an empty area in the tab and select **Restore All Default** (Windows) or **Restore Default** (Mac).
Camtasia restores any deleted application defaults and maintains your existing user-created presets and Favorites.

Build a Video Template to Share

Create and share a video template to help collaborators quickly build consistent and professional videos.

Enhancements to Consider

Create a new project or update an existing project to save as a video template. Include common video enhancements such as:

Enhancement	Description	Camtasia Asset Category
Placeholders	Placeholders guide video creators on the type of content to replace in the template. Placeholders preserve the canvas position, transitions, effects, audio points, and animations when possible.	
Intros and Outros	Add a consistent title to introduce a video series or to brand videos on your channel. Combine title text with elements in the UI Kit (such as a subscribe button) to drive engagement to your channel or page.	Titles, UI Kit
Lower Thirds	Overlay animations and text to introduce the speaker or scene in a video.	Titles
Background Video	Looping animations or video clips to use as a background or scene in a video.	Dynamic Backgrounds, Footage
Background Music	Instrumental or vocal tracks to use as an audio background or to set a mood for your video.	Music
Effects	Short clips with an alpha channel to accent media. Add callouts or emphasis bursts and sound effects to standardize click effects across a tutorial or video series.	Callouts, Emphasis Bursts, Sound Effects
Device Frames	Computer or mobile device images to provide context around a screenshot or video clip.	Device Frames


Camtasia includes many professionally-designed assets to use as enhancements. Select **Media tab > Assets subtab** to browse categories and assets. To learn more, see [Enhance Your Video with Camtasia Assets \(https://www.techsmith.com/learn/tutorials/camtasia/camtasia-assets/\)](https://www.techsmith.com/learn/tutorials/camtasia/camtasia-assets/).

Tip: Download premade templates.


Premade, professionally designed templates are available on the Camtasia Assets website. To import a template from Camtasia Assets, see [How to Use a Template \(https://www.techsmith.com/learn/tutorials/camtasia/use-a-template/\)](https://www.techsmith.com/learn/tutorials/camtasia/use-a-template/).

Create a Video Template

1. Select **File > New Project**.
2. To add a placeholder, drag the cursor to the desired location on the timeline and select **Edit > Add Placeholder** or press **P** on the keyboard.



3. Camtasia adds the placeholder to the timeline. In the Properties panel, enter a title and a note to instruct video creators on the type of content or media specifications for replacing the clip.



Note: The title appears on the canvas and timeline, but notes appear only in the Properties panel.

4. Add other desired enhancements in the project on the timeline or canvas.
5. To save the project as a template, select **File > Save Project as Template**.

6. Enter a template name and click **OK**.

To share the the video template, see [Share a Video Template](#).


Tip: Customize the template thumbnail.

To customize the thumbnail for the template shown in the Template Manager, drag the playhead to the desired location on the timeline before saving or exporting.

Edit a Video Template

Ensure video creators maintain your video standards by updating your video templates with the latest branding, logos, and other video updates.

1. Select **File** (Windows) or **Camtasia** (Mac) > **Manage Templates**.
2. The Template Manager dialog opens. Complete one of the following:
 - o Select a template and click **New from Template**.
 - o Click the **+** to select a template file (.camtemplate) from your computer and click **Open**.



3. After making the desired edits, select **File** > **Save Project as Template**.
4. Enter a template name and click **OK**.

Tip: Strategies to save template changes:

- To replace the current template, save with the same file name.
- To designate a template version, add a number to the end of the file name.

Share a Video Template

Export as a single template (.camtemplate) or add templates, source files, and media to a [Camtasia Package](https://www.techsmith.com/learn/tutorials/camtasia/package-share-camtasia-resources/) (.campackage) to share with others.

1. Open a saved template in Camtasia Editor.
2. Select **File > Export > Template**.
3. Browse to a location and enter a file name.
4. Click **Save**.

Camtasia exports a template (.camtemplate). To build a new video from this template, see [How to Use a Template](https://www.techsmith.com/learn/tutorials/camtasia/use-a-template/).

Build Your Color Palette (Themes)

Learn how to create and apply themes to quickly apply styles to callouts, shapes, arrows, and assets to match your personal or corporate brand.

Themes Overview

A theme is a set of preset fonts, colors, and logos used to customize assets in your video. Quickly apply theme presets to maintain consistency across a series of videos.


[Export](#) and share individual themes with your team or add to a [Camtasia package](#) (https://www.techsmith.com/learn/?post_type=tutorial&p=182342) to share custom resources.

Create a Theme

1. Select **File** (Windows) or **Camtasia menu** (Mac) > **Manage Themes**.
2. The Theme Manager appears. Click the **Create New Theme** button.



3. Enter a theme name and click **OK**.
4. Click to select the **Colors** tab.




5. Set the theme colors:
 - **Change a Color:** Click a dropdown and select a color from the palette, enter a Hex value, a RGB value, or click the color picker to select a color on the screen.
 - **Add a New Color:** Click the **Add** button and select a color.



- **Annotation Background:** Select a theme color to use as the annotation fill color. See [Apply a Theme](#).
- **Delete a Color:** Click the  icon.


6. Click to select the **Fonts** tab.



7. Set the theme fonts:

- **Change a Font:** Click the dropdown and select a font.
- **Add a New Font:** Click the **Add** button and select a font.
- **Delete a Font:** Click the  icon.

8. On the **Logo** tab, click the **Browse** button to select an image such as a corporate logo, icon, or company name.




9. Click **Save** to save the changes to the theme.

Download Additional Themes Online



Customizable themes instantly make your video look more professional and polished with coordinated colors and fonts. No graphic design experience necessary!

Apply a Theme

1. Click to select the annotation or asset on the canvas or timeline.
2. Click the **Properties** button to open the Properties panel.
3. Complete one of the following to apply a theme or theme property:
 - **Automatically Apply Theme Settings:** Select a theme from the **Theme** dropdown.



- **Apply a Specific Theme Setting (color, font, etc.):** Select a theme from the properties dropdown you want to change. If the theme is available for the property, the theme presets appear in the dropdown.




On Mac, you must have the system color picker disabled to view the theme colors. Select **Camtasia menu > Settings** (macOS 13 or later) or **Preferences** (macOS 12 or earlier) > **General tab > uncheck the Enable System Color Picker option.**

Tip: Apply theme settings to grouped properties to create a custom asset.

1. Group annotations on the timeline. See [How to Use Group Tabs \(https://www.techsmith.com/learn/?post_type=tutorial&p=182316\)](https://www.techsmith.com/learn/?post_type=tutorial&p=182316).
2. Link properties in the Quick Property Editor to create subgroups and apply theme elements. See [Create Custom Assets \(https://www.techsmith.com/learn/?post_type=tutorial&p=182311\)](https://www.techsmith.com/learn/?post_type=tutorial&p=182311).

Add Annotations Based on a Theme

1. Click the **Annotations** tab.
2. Select **Callouts, Arrows and lines**, or **Shapes** subtab.
3. Select a theme from the **Theme** dropdown.




4. Camtasia automatically applies the theme colors and fonts to the annotations on the tab. Drag an annotation onto the timeline to add to your video.

Edit a Theme

1. Select **File** (Windows) or **Camtasia menu** (Mac) > **Manage Themes**.
2. The Theme Manager appears. Select a theme from the **Theme** dropdown.
3. Make desired edits to theme colors, fonts, and logos.
4. To change the theme name, click the gear icon  and select **Rename**.
5. Click **Save**.

Export a Theme

1. Select **File** (Windows) or **Camtasia menu** (Mac) > **Manage Themes**.
2. The Theme Manager appears. Click the gear icon  and select **Export Theme**.




3. Select the location to save the .camtheme file and click **Save**.

Camtasia saves the theme to your computer.

Import a Theme


1. Select **File** (Windows) or **Camtasia menu** (Mac) > **Manage Themes**.
2. The Theme Manager appears. In the Theme dropdown, select a theme to import.
3. Click the gear icon  and select **Import Theme**.



4. Locate the .camtheme file and double-click the file to open into Camtasia.
Camtasia imports the .camtheme file into the Theme Manager.

Download Additional Themes

To download additional premade themes, visit the [Camtasia Assets website](https://library.techsmith.com/en/camtasia) (<https://library.techsmith.com/en/camtasia>) and select **Themes**.



Click the **Send to Camtasia** button to add the theme to Camtasia. The theme appears in the **Themes** dropdown in the Properties panel and in **File > Manage Themes** dialog.

Package & Share Camtasia Resources

Create a Camtasia Package (.cpackage) to back up and share your Camtasia resources such as templates, shortcuts, libraries, themes, and presets.

Create a Camtasia Package (.cpackage) to:


- Share assets with others to quickly create consistent and professional videos.
- Deploy brand assets and resources across multiple computers, teams, or organizations.
- Back up your Camtasia resources.

Packages can include: [templates](https://www.techsmith.com/learn/?post_type=tutorial&p=182343) (https://www.techsmith.com/learn/?post_type=tutorial&p=182343), [shortcuts](https://www.techsmith.com/learn/?post_type=tutorial&p=182359) (https://www.techsmith.com/learn/?post_type=tutorial&p=182359), [libraries](https://www.techsmith.com/blog/?post_type=tutorial&p=182344) (https://www.techsmith.com/blog/?post_type=tutorial&p=182344), [themes](https://www.techsmith.com/learn/?post_type=tutorial&p=182345) (https://www.techsmith.com/learn/?post_type=tutorial&p=182345), [tool presets](https://www.techsmith.com/learn/?post_type=tutorial&p=182310) (https://www.techsmith.com/learn/?post_type=tutorial&p=182310), and export presets.

Export a Package

Export a Camtasia Package (.cpackage) to share the video resources you used, such as templates and asset libraries, to quickly create consistent and professional videos.

1. Open a new or existing project in Camtasia.
2. Select **File > Export > Package**.
3. The Package Manager appears. Select the Camtasia resources to export.



4. Click **Export**.

5. Enter a package name and click **Save**.

Camtasia saves the .cpackage file. To open the Camtasia Package on another computer, see [Import a Package](#).

Import a Package

Import a Camtasia Package (.cpackage) to add video resources such as templates, shortcuts, libraries, themes, tool presets, and export presets into Camtasia.


Note: Shortcuts are not cross-platform compatible.

1. Open a new or existing project in Camtasia.
2. Select **File > Import > Package**.
3. Select the Camtasia Package file (.cpackage) to import and click **Open**.
4. Click **Replace** (Windows and Mac), **Skip** (Windows and Mac), or **Keep Both** (Mac only) if prompted in the progress dialog.
5. A dialog appears and displays a list of imported resources. Click **OK**.
Camtasia imports the selected resources.

Customize Shortcuts


Learn how to customize the Camtasia recording and editing keyboard shortcuts.

Speed up video creation based on your preferences by customizing the recording and editing shortcuts. Export your customized shortcut sets to share with others or to transfer to another computer.



Edit Shortcuts

1. To customize shortcuts:
 - **Windows:** Select **Edit > Preferences > Shortcuts tab**.
 - **Mac:** Select **Camtasia > Preferences > Shortcuts tab**.
2. Click in the field and press the desired key combination.



Note: If the keyboard shortcut entered is already assigned to another customizable shortcut, Camtasia unassigns the shortcut for that command and displays a message.

If the keyboard shortcut entered is reserved by system controls or another program, a message appears. Please enter another keyboard shortcut combination.

Delete Shortcuts

- To delete a shortcut, click in the field and click the **Delete** button.



- To delete a shortcut set (Mac only), select the set from the **Shortcut Set** dropdown. Click the  icon and select **Delete**.

Revert to Previous Shortcut

- To revert to the previously assigned shortcut, click the **Revert** button.



- To restore all shortcuts to the original Camtasia defaults:
 - Windows:** Click the **Restore defaults** button.
 - Mac:** Select **TechSmith Camtasia Default** from the **Shortcut Set** dropdown.

Export Editor Shortcuts

Note: Shortcut sets are not cross-platform compatible.

- Select **Edit (Windows) > Preferences > Shortcuts tab** or **Camtasia (Mac) > Preferences > Shortcuts tab**.
 - On Mac, select the set to export from the **Shortcut Set** dropdown.
- Click the  icon and select **Export**.
- Enter a file name, location, and click **Save**.


Camtasia saves the Camtasia Shortcuts file (.camshortcuts on Windows and .camsc on Mac).

Import Editor Shortcuts

Note: Shortcut sets are not cross-platform compatible.

1. Select **Edit (Windows) > Preferences > Shortcuts tab** or **Camtasia (Mac) > Preferences > Shortcuts tab**.
2. Click the  icon and select **Import**.
3. Select a Camtasia Shortcuts file (.camshortcuts on Windows and .camsc on Mac) and click **Open**.

On Windows, Camtasia overwrites the existing keyboard shortcuts with the new shortcut set. On Mac, Camtasia adds the shortcut set to the dropdown.




Create Custom Assets

Create your own custom assets to reuse across multiple projects. Share custom assets with your team to maintain brand identity or a consistent look and feel.

Create a Custom Asset

Group media on the timeline to create your own custom asset.


1. Add logos and annotations such as callouts, shapes, and lines to the canvas or timeline to build the custom asset.



2. Select all media to include in the custom asset. Right-click (Windows) or Control+click (Mac) the selection and select **Group**. See [How to Use Group Tabs \(https://www.techsmith.com/learn/?post_type=tutorial&p=182316\)](https://www.techsmith.com/learn/?post_type=tutorial&p=182316).
3. Click the **Properties** button. The Properties panel displays the editable properties in the group. Complete any of the following to edit the group properties:




- Apply a theme to the entire group. See [Build Your Color Palette \(Themes\) \(https://www.techsmith.com/learn/?post_type=tutorial&p=182345\)](https://www.techsmith.com/learn/?post_type=tutorial&p=182345).
- Edit properties individually within the group.



Customize Asset Properties

The Quick Property Editor allows you to customize the display and organization of properties for a custom asset. Use the Quick Property Editor to:

- Control which properties are available for editing.
- Link assets together to quickly edit multiple assets at one time.
- Create your own descriptive labels for each asset or linked set of assets.




Option

Steps

Link Assets

Link multiple assets together to edit at one time.



1. Drag the **Reorder** icons up or down to move the assets to be linked next to each other.

Note: Only assets of the same type can be linked. For example, callouts with other callouts or text with other text can be linked.

2. Click the **Link** icon  to link an asset with the one above it. Each linked “child” below inherits the properties of the “parent” above it.
3. Repeat to link any additional assets.
4. Click **Save**.

Unlink Assets:


1. Click the **Unlink** icon  to edit the properties individually.
2. Click **Save**.

Label Assets

Add descriptive labels to provide context for individual parts of the custom asset.

For example:

- Distinguish similar items from each other.
- Indicate text to enter, such as “Name” and “Job title.”




1. In the **Label** field, enter the desired label.
2. Click **Save**.

Assign Theme Elements

Control which element from a theme applies to each property.

For example, assign “Background 1” from your Company’s theme to one property and “Accent 1” to another property to set their colors.



1. In the Properties panel, apply a theme to the group.
2. Click the **Open Quick Property Editor** button.



3. Click the gear icon and select a theme element from the dropdown.

- o **Green gear** : A theme element is applied to the property. Changes to the theme affect the property.
- o **White gear** : No theme element is applied to the property.

4. Click **Save**.

Edit Visible Properties

Control which properties are shown in the Properties panel for editing.


For example, remove assets that display company name or brand colors from Visible Properties to prevent them from being edited.

1. Edit the asset and its properties as desired.

2. Click the **Remove Property**



icon to move the property from Visible Properties to Available Properties. The



property does not appear in the Properties panel and cannot be edited.

3. Click the **Add Property** icon  to include a property in the Properties panel and allow it to be edited.
4. Click **Save** to view your changes in the Properties panel.


Tip: Reuse and share your custom assets with others.

- To reuse custom assets across projects, add them to a Library. See [Reuse Media Across Projects \(Asset Libraries\)](https://www.techsmith.com/learn/?post_type=tutorial&p=182344) (https://www.techsmith.com/learn/?post_type=tutorial&p=182344).
- To share a custom asset with others, add it to a Library and then export the Library as a Camtasia Package. See [Package & Share Camtasia Resources](https://www.techsmith.com/learn/?post_type=tutorial&p=182342) (https://www.techsmith.com/learn/?post_type=tutorial&p=182342).

Learn About Camtasia Files

Learn about Camtasia project and recording files along with best practices to keep your project files organized.

Camtasia File Types

File Format	Description
Recording Files (TREC) 	<p>Default file format produced after recording in Camtasia Recorder. TREC stores audio, screen recording, camera recording, and metadata into a single package.</p> <p>Note: TREC files can only be opened in Camtasia.</p>
Project Files (TSCPROJ) 	<p>Video project file that saves any edits completed on the timeline and references the location on your computer of any recordings and source files in the Media Bin.</p> <p>Open the TSCPROJ project file at any time to update, collaborate, or export a video to share.</p> <p>Note: TSCPROJ files can only be opened in Camtasia.</p>

Manually Save Recordings

By default, Camtasia automatically names and saves all TREC recordings to the Camtasia folder located here:

- **Windows:** C:\Users\username\Documents\Camtasia
- **Mac:** Users/username/Movies/Camtasia 2023/Temporary Recordings

You can configure Camtasia Recorder to open a Save dialog to enter a file name and location for each TREC recording file after recording.

Windows:

1. In Camtasia Recorder, select **Tools > Options**.
2. The Recorder Preferences dialog appears. Click the **Files** tab.
3. Select the **Prompt for file name** option.
4. Click **OK**.

Mac:


1. Select **Camtasia 2023 menu > Settings** (macOS 13 or later) or **Preferences** (macOS 12 or earlier) > **Recording tab**.
2. In the **After recording** dropdown, select the **Prompt to Save** option.

After stopping the recording, a Save dialog appears where you can enter a file name and save the recording to your desired location.


File Management Tips

Video file management can be overwhelming. Here are some tips and common workflows we use at TechSmith to help you get started:

- When starting a new video project, set up a directory to save all the source files such as audio, recordings, scripts, etc. into one location for your video project. Here’s an example folder structure:



- After recording, move the recording files (TREC) from the default Camtasia folder into your video project directory. To skip this step, you can set Camtasia Recorder to prompt for a file name and location after recording, see [Manually Save Recordings](#).



- To add recordings and other media into your video project file (TSCPROJ), select **Camtasia > File > Import >**

Media. Select the files in your project directory. Camtasia imports the files into the Media Bin. To learn more about adding source files to your project and supported file formats, see [Import & Manage Your Media \(Media Bin\)](https://www.techsmith.com/learn/?post_type=tutorial&p=182296) (https://www.techsmith.com/learn/?post_type=tutorial&p=182296).

- To archive a video project, create a backup, or to move the project to another computer, select **File > Export > Zipped Project** (Windows) or **File > Export > Project for Windows** (Mac) to save the final project as a ZIP file.
 - **Important:** Make sure you can open the zipped project in Camtasia (**File > Import > Zipped Project**) and that the project contains all of the source files before deleting any files from your computer.
- Do you frequently reuse the same video assets? See [Reuse Media Across Projects \(Asset Libraries\)](https://www.techsmith.com/learn/?post_type=tutorial&p=182344) (https://www.techsmith.com/learn/?post_type=tutorial&p=182344) to learn how to save assets to the Library for reuse across all of your Camtasia video projects.

Other Camtasia Files

Type	Description
Asset Files	<p>Enhance your Camtasia (https://www.techsmith.com/video-editor.html) videos with assets downloaded from the TechSmith Assets for Camtasia website or save your own asset files (https://www.techsmith.com/learn/?post_type=tutorial&p=182344).</p> <p>See Download & Install TechSmith Assets (https://www.techsmith.com/learn/?post_type=tutorial&p=182349).</p>
Library	<p>Download or save intros, animated backgrounds, icons, lower thirds, music, groups, annotations, and more to the Library to use in other projects.</p> <p>See Reuse Media Across Projects (Asset Libraries) (https://www.techsmith.com/learn/?post_type=tutorial&p=182344).</p>
Packages	<p>Create a Camtasia Package (.campaackage) to back up and share your Camtasia resources.</p> <p>See Package & Share Camtasia Resources (https://www.techsmith.com/learn/?post_type=tutorial&p=182342).</p>
Templates	<p>Create and share a video template to help video collaborators quickly build consistent and professional videos.</p> <p>See Build a Video Template to Share (https://www.techsmith.com/learn/?post_type=tutorial&p=182343) or How to Use a Template (https://www.techsmith.com/learn/?post_type=tutorial&p=182297).</p>
Themes	<p>Quickly apply theme presets containing colors, fonts, and logos to maintain consistency across a series of videos.</p> <p>See Build Your Color Palette (Themes) (https://www.techsmith.com/learn/?post_type=tutorial&p=182345).</p>

Export File Formats	<p>Export and share a video file based on the sequence of media (recordings, video clips, audio clips, images, and effects) on the timeline.</p> <p>See Export & Share Your Video (https://www.techsmith.com/learn/?post_type=tutorial&p=182298) or Export an Audio File (https://www.techsmith.com/learn/?post_type=tutorial&p=196536).</p>
Import File Formats	<p>Import different media types into your project to use on the project timeline.</p> <p>See Import & Manage Your Media (Media Bin) (https://www.techsmith.com/learn/?post_type=tutorial&p=182296).</p>

Learn About Standalone Projects


Keep your Camtasia project files organized with standalone project folders.

About Camtasia Projects

The Camtasia Project file format (.tscproj) allows you to quickly [save](#) and [share](#) your video project files.

- Share a Camtasia standalone project to build and collaborate on a video with others.
- Share a Camtasia standalone project to work on a video across computers, such as between work and personal computers.

The standalone project includes all media and assets used in the video project. When you save a new Camtasia project, the **Create standalone project** option is selected by default.



Save a Project

1. Select **File** (Windows) or **Camtasia 2022** (Mac) > **Save As**.
2. The Save As dialog appears. Enter a project name and choose a file location.
3. Make sure the **Create standalone project option** is enabled. This options includes all media and assets used in the video in the project file.
4. Click **Save**.

Share a Project

Create a zip file to back up or share your project. Zip files contain the Camtasia Project file (.tscproj), content in the Media Bin, and enhancements added to the project.

Note: To export all Camtasia resources, including asset libraries, presets, themes, and templates, see [Package and Share Camtasia Resources \(https://www.techsmith.com/learn/?post_type=tutorial&p=182342\)](https://www.techsmith.com/learn/?post_type=tutorial&p=182342).


▼ Share a Project to the Same Platform

1. In Camtasia Editor:
 - Windows: Select **File > Export > Zipped Project**.
 - Mac: Select **File > Save As**.
2. Enter the project name and choose a file destination.
3. Click **Save**.

Camtasia saves a zipped project file to your computer.

▼ Share a Project to Another Platform

1. In Camtasia Editor, select **File > Export > Project for Windows/Mac**.
2. If you receive a warning about incompatibility or partially supported media in the project, click **Continue** to export the project.



3. Enter the project name and choose a file destination.
4. Click **OK**.

Camtasia saves a zipped project file to your computer.

Note: To learn about media and effects that are not supported across platforms, see [Incompatible Media and Effects](#).

Open a Project


▼ Import a Project on the Same Platform

1. Select **File > Import > Zipped Project**.
2. Browse to the location of the zipped file.
 - Windows: Click **Import**.
 - Mac: Click **Open**.
3. A save dialog appears. Click **Save** to import the project including all media and assets to the selected location.

Camtasia opens the project.

▼ Import a Project on Another Platform

1. In Camtasia Editor, select **File > Import > Zipped Project**.
2. If you receive a warning about incompatible or partially compatible media in the project, click **Continue** to open the project.



Incompatible media displays as a placeholder on the timeline. If you open the project on the original platform, the media is visible.

Note: To learn about media and effects that are not supported across platforms, see [Incompatible Media and Effects](#).




Incompatible Media and Effects

The Camtasia Project file format (.tscproj) is cross-platform compatible. However, not all media and effects are supported across platforms.

Discover the Properties Panel



The Properties panel in Camtasia allows you to customize media, annotations, behaviors, effects, and assets added to the timeline.



The Properties panel shows the available options to customize [media](https://www.techsmith.com/learn/tutorials/camtasia/import-manage-media/) (<https://www.techsmith.com/learn/tutorials/camtasia/import-manage-media/>), [annotations](https://www.techsmith.com/learn/tutorials/camtasia/annotations/) (<https://www.techsmith.com/learn/tutorials/camtasia/annotations/>), [behaviors](https://www.techsmith.com/learn/tutorials/camtasia/animation-behaviors/) (<https://www.techsmith.com/learn/tutorials/camtasia/animation-behaviors/>), [effects](https://www.techsmith.com/learn/tutorials/camtasia/visual-effects/) (<https://www.techsmith.com/learn/tutorials/camtasia/visual-effects/>), and [assets](https://www.techsmith.com/learn/tutorials/camtasia/install-assets/) (<https://www.techsmith.com/learn/tutorials/camtasia/install-assets/>) on the timeline or canvas.

Option	Edit Properties
<p>Open Properties (media, annotations, behaviors, or effects)</p>	<ol style="list-style-type: none"> Click to select media on the timeline. For effects and behaviors, click the Show Effects tray icon on the media and click the effect or behavior.  <ol style="list-style-type: none"> Click the Properties button. 
<p>Edit Quick Properties for Assets Edit properties such as titles, logos, colors, text, and more for assets.</p>	<ol style="list-style-type: none"> Click to select asset on timeline. Click the Properties button.  <ol style="list-style-type: none"> On the Quick Properties tab, edit the desired properties.  <p>To learn how to customize the properties for groups and assets, see Create Custom Assets (https://www.techsmith.com/learn/tutorials/camtasia/create-custom-assets/).</p>

View Effect Properties
If multiple effects are

1. Click to select media on timeline.

Option	Edit Properties
<p>added to media, you may have to scroll to view all the properties available.</p> 	<ol style="list-style-type: none"> Click the Properties button.  Drag the scroll bar in the Properties panel. 
<p>Reset to Default Settings</p>	<p>Click the  button in the properties.</p>
<p>Preview Effects</p> <p>Turn an effect, transition, or behavior on/off. Disabled effects are not applied in the preview or exported video.</p>	<ol style="list-style-type: none"> Click to select media on timeline. For effects or behaviors, click the Show Effects tray icon on the media. Click to select the effect or behavior.  Click the Properties button.  Click the Enable/Disable button to turn the effect on or off. 

Option	Edit Properties
<p>Delete</p> <p>Remove the applied effect, animation, or behavior from media on the timeline.</p>	<p>Click the  button in the properties.</p>  <p>To undo the delete:</p> <ul style="list-style-type: none"> • Press Ctrl+Z (Windows) or Command+Z (Mac). • Select Edit > Undo.
<p>Add a Preset</p> <p>Save annotations, behaviors, and effects.</p>	<ol style="list-style-type: none"> 1. Click an enhancement tab such as the Annotations tab > Callouts subtab. 2. Drag an enhancement onto the canvas or media on the timeline. 3. In the properties, customize the enhancement as desired.  <ol style="list-style-type: none"> 4. Click the  to save the custom enhancement properties as a new preset. <div style="border: 1px solid #ccc; padding: 10px; margin-top: 10px;"> <p>Note: To view annotation presets, select Annotations tab > Style and select User from the Style dropdown. See Customize Camtasia (Favorites & Presets) (https://www.techsmith.com/learn/tutorials/camtasia/customize-camtasia/).</p> </div>

Camtasia Shortcuts

Quickly reference the keyboard shortcuts in Camtasia.

Note: Shortcuts are tested on a QWERTY keyboard. Some shortcuts may not work with the keyboard you use. To customize the shortcuts:

- On Windows, select **Edit > Preferences > Shortcuts tab**.
- On Mac, select **Camtasia > Settings**.

See [Customize Camtasia Shortcuts](#)

(<https://www.techsmith.com/learn/tutorials/camtasia/customize-camtasia-shortcuts/>).

Recorder Options

Option	Customizable	Windows Shortcut	Mac Shortcut
New recording	No	Ctrl+R	Ctrl+R
Start/pause recording	Yes	F9	Command+Shift+2
Stop recording	Yes	F10	Command+Option+2
Add marker while recording	Yes	Ctrl+M	Shift+Ctrl+Option+Command+M

Animations and Effects

Option	Customizable	Windows Shortcut	Mac Shortcut
Add last used transition	Yes	Shift+T	Shift+T
Add custom animation	Yes	Shift+A	Shift+A
Jump to next animation	Yes	Alt+I	Option+I
Jump to previous animation	Yes	Shift+I	Shift+I
Start/stop narration recording	Yes	Ctrl+Shift+V	—

Canvas Options

Option	Customizable	Windows Shortcut	Mac Shortcut
Zoom in on canvas	Yes	Ctrl+Equal sign -Or- Scroll Wheel	Command+Equal sign -Or- Scroll Wheel
Zoom out on canvas	Yes	Ctrl+Minus -Or- Scroll Wheel	Command+Minus -Or- Scroll Wheel
Center canvas	Yes	Alt+C	Option+C
Preview media outside of group	Yes (Mac only)	—	Shift+Command+G
Pan to here	Yes (Mac only)	—	Command+Option+Z
Scale to fit	Yes (Mac only)	—	Command+Option+F
Scale to fill	Yes (Mac only)	—	Shift+F
Pan and scale to 200%	Yes (Mac only)	—	Command+Option+4
Pan and scale to 100%	Yes (Mac only)	—	Command+Option+3
Pan and scale to 50%	Yes (Mac only)	—	Command+Option+2
Pan and scale to 25%	Yes (Mac only)	—	Command+Option+1
Enable/disable canvas snapping	Yes (Windows only)	Ctrl+Semicolon	Command+Semicolon
Move selected media left	No	Left Arrow Key	Left Arrow Key
Move selected media right	No	Right Arrow Key	Right Arrow Key
Move selected media up	No	Up Arrow Key	Up Arrow Key
Move selected media down	No	Down Arrow Key	Down Arrow Key

Move media 10 pixels	No	Shift+Arrow Key	Shift+Arrow Key
Change size of selected media on canvas	No	Ctrl+Scroll Wheel	—
Exit full screen canvas view	No	Esc	Esc
Maintain aspect ratio while resizing media (excludes annotations)	No	Drag corner handle on selected media to resize	Drag corner handle on selected media to resize
Override aspect ratio when resizing (excludes annotations)	No	Hold Shift and drag corner handle on selected media to resize	Hold Shift and drag corner handle on selected media to resize
Resize media with aspect ratio and maintain center point (excludes annotations)	No	Hold Ctrl and drag corner handle on media to resize	Hold Command and drag corner handle on media to resize
Freely rotate media (3D)	No	<ol style="list-style-type: none"> 1. Select media on canvas. 2. Hold Shift+Ctrl while dragging media. <div style="border-left: 2px solid green; padding-left: 10px; margin-top: 10px;"> <p>Note: Do not use side or rotate handles.</p> </div>	—

Program Options

Option	Customizable	Windows Shortcut	Mac Shortcut
Show/hide tools panel	Yes	Ctrl+1	Command+1
Show/hide properties panel	Yes	Ctrl+2	Command+2
Attach/detach timeline	Yes	Ctrl+3	Command+3 (On Timeline Navigation tab on Mac)
Open media bin subtab	Yes	B	B

Open Camtasia assets subtab	Yes	E	E
Open library subtab	Yes	R	R
Open favorites tab	Yes	F	F
Open annotations tab	Yes	N	N
Open transitions tab	Yes	T	T
Open behaviors tab	Yes	O	O
Open animations tab	Yes	A	A
Open cursor effects tab	Yes	U	U
Open voice narration tab	Yes	V	V
Open audio effects tab	Yes	D	D
Open visual effects/video effects tab	Yes	X	X
Open gesture effects tab	Yes (Mac only)	—	G
Open captions tab	Yes	C	—
Launch home dialog	Yes	Ctrl+H	Command+Period
Launch preferences dialog	Yes (Windows only)	Ctrl+Comma	Command+Comma
Launch recorder	Yes (Windows only)	Ctrl+R	Ctrl+R
Launch Camtasia Audiate recorder	Yes (Windows only)	Ctrl+Alt+A	—
Launch Snagit Image Capture	Yes (Windows only)	Ctrl+Alt+S	—
Import package	Yes	Ctrl+Shift+P	Ctrl+Shift+P
Export package	Yes	Ctrl+Shift+E	Ctrl+Shift+E

Maximize or de-maximize window (Mac)	Yes (Mac only)	See below – Maximize/Minimize window (Windows)	Command+Shift+M
Hide other programs	No	—	Command+Option+H
Maximize/Minimize window (Windows)	No	Maximize: Windows logo key+Up Arrow Minimize: Windows logo key+Down Arrow	See above – Maximize or de-maximize window (Mac)
Exit/quit Camtasia	No	Alt+F4	Command+Q
Close window	No	—	Command+W
Symbols and emojis	No	—	Ctrl+Command+Spacebar
Enter full screen program	No	—	Command+Shift+F
Display system menu	No	Alt+Spacebar	—
Activate menus	No	Alt+First letter of menu	—
Remove focus or close current control, menu, or dialog box	No	Esc	Esc

Project Options

Option	Customizable	Windows Shortcut	Mac Shortcut
Import media into media bin	Yes	Ctrl+I	Command+I
Export frame as	Yes	Ctrl+F	Ctrl+F
Export to local file (Windows) Export (Mac)	Yes	Ctrl+E	Command+E
Export frame at playhead	Yes	Ctrl+Shift+F	Ctrl+Shift+F
New project	No	Ctrl+N	Command+N
Open project	No	Ctrl+S	Command+O
Save project	No	Ctrl+S	Command+S

Timeline Editing

Option	Customizable	Windows Shortcut	Mac Shortcut
Group	Yes	Ctrl+G	Command+G
Ungroup	Yes	Ctrl+U	Command+U
Add audio point	Yes (Mac only)	—	Ctrl+Shift+A
Open group	Yes (Windows only)	Ctrl+Shift+G	Ctrl+Shift+G
Close group	Yes (Windows only)	Ctrl+Shift+U	Ctrl+Shift+U
Silence audio	Yes	Shift+S	Option+S
Restore audio	Yes	Shift+R	Option+R
Split selected media at playhead	Yes	S	Command+T
Split all tracks at playhead	Yes	Ctrl+Shift+S	Command+Shift+T
Stitch selected media	Yes	Ctrl+Alt+I	Command+Option+I
Remove all stitches from selected track	Yes	Ctrl+Shift+\	Command+Shift+\
Add annotation	Yes	Shift+N	Shift+N
Extend frame	Yes (Windows only)	Shift+E -Or- Hold Alt and drag end of clip	Hold Option and drag end of clip
Duration	Yes (Mac only)	—	Ctrl+D
Copy Properties	Yes	—	Command+Shift+C
Paste Properties	Yes	—	Command+Shift+V

Copy Effects	Yes (Windows only)	—	—
Paste Effects	Yes (Windows only)	—	—
Add selection to library	No	Ctrl+Shift+A	—
Add placeholder	Yes	P	P
Convert to placeholder	Yes	Ctrl+Alt+P	—
Deselect all	Yes (Windows only)	Ctrl+Shift+D	Command+Shift+A
Select all	No	Ctrl+A	Command+A
Ripple delete <ul style="list-style-type: none"> Copies to clipboard (Mac only) No gap Stitches media together on timeline Deletes selection and shifts all timeline media left 	Yes (Windows only)	<ol style="list-style-type: none"> Make a selection on timeline. Press Ctrl+Delete or Backspace. 	<ol style="list-style-type: none"> Make a selection on timeline. Press Command+Delete or Backspace.
Cut <ul style="list-style-type: none"> Copies to clipboard No gap (Windows only) Stitches media together on timeline (Windows only) 	No	Ctrl+X	Command+X
Duplicate	Yes (Windows only)	Ctrl+D	Command+D
Copy	No	Ctrl+C	Command+C
Delete Leaves space on timeline	No	Delete	Delete

Paste	No	Ctrl+V	Command+V
Redo	No	Ctrl+Y	Command+Shift+Z
Undo	No	Ctrl+Z	Command+Z
Pan	No	Hold Spacebar and drag canvas	Hold Spacebar and drag canvas
Crop	No	Hold Alt and drag handles	Hold Alt and drag handles
Open media bin tab	No	B	B
Increase/decrease properties	No	Drag handles/sliders to adjust number -Or- Type number -Or- Click number and use Up/Down Arrow to increase or decrease number	Drag handles/sliders to adjust number -Or- Type number -Or- Click number and use Up/Down Arrow to increase or decrease number

Timeline Navigation

Option	Customizable	Windows Shortcut	Mac Shortcut
Play/pause/stop video	No	Spacebar	Spacebar
Return playhead	Yes	Ctrl+Alt+M	Ctrl+Option+Spacebar
Move playhead to previous clip	Yes	Ctrl+Alt+Comma	Ctrl+Comma
Move playhead to next clip	Yes	Ctrl+Alt+Period	Ctrl+Period
Step backward on timeline	Yes	Comma	Comma
Step forward on timeline	Yes	Period	Period
Zoom in	Yes	Ctrl+Shift+Equal -Or- Ctrl+Scroll Wheel	Command+Shift+Equal -Or- Command+Scroll Wheel
Zoom out	Yes	Ctrl+Shift+Minus -Or- Ctrl+Scroll Wheel	Command+Shift+Minus -Or- Command+Scroll Wheel

Zoom to fit Shows all media on timeline	Yes	Ctrl+Shift+7 -Or- Ctrl+Scroll Wheel	Command+Shift+0 -Or- Command+Scroll Wheel
Zoom to max Shows maximum timeline view	Yes	Ctrl+Shift+9 -Or- Ctrl+Scroll Wheel	Command+Shift+9 -Or- Command+Scroll Wheel
Make timeline selection	No	Hold Ctrl and drag playhead	Hold Command and drag playhead
Zoom to selection	Yes	Ctrl+Shift+8	Command+Shift+8
Jump to beginning of timeline Move playhead to beginning	Yes	Ctrl+Home	Command+Return
Jump to end of timeline Move playhead to end	Yes	Ctrl+End	Command+Shift+Return
Jump to specific time	Yes	—	—
Extend selection to next clip	Yes	Ctrl+Shift+Alt+Right Arrow	Command+Shift+Option+Period
Extend selection to previous clip	Yes	Ctrl+Shift+Alt+Left Arrow	Command+Shift+Option+Comma
Extend selection range left	Yes	Shift+Comma	Shift+Comma
Extend selection range right	Yes	Shift+Period	Shift+Period
Move up or down through tracks	No	Scroll Wheel -Or- Drag scroll bar	Scroll Wheel -Or- Drag scroll bar
Increase track heights	Yes	Alt+Equal sign	Option+Equal sign
Decrease track heights	Yes	Alt+Minus	Option+Minus
Extend selection to timeline beginning	Yes (Windows only)	Ctrl+Shift+Home	—
Extend selection to timeline end	Yes (Windows only)	Ctrl+Shift+End	—
Select succeeding media	Yes	Alt+Right Arrow	—
Select preceding media	Yes	Alt+Left Arrow	—

Select all media to left of playhead	Yes (Windows Only)	Ctrl+Alt+J	—
Select all media to right to right of playhead	Yes (Windows Only)	Ctrl+Alt+L	—
Select all timeline to left	Yes (Mac Only)	—	Ctrl+Shift+Left Arrow
Select all timeline to right	Yes (Mac Only)	—	Ctrl+Shift+Right Arrow
Increase reverse playback speed	Yes (Windows only)	J	J
Decrease reverse playback speed	No	Shift+J	Shift+J
Step backward one frame	No	K+J	K+J
Step backward 1/2 second	No	Shift+K+J	Shift+K+J
Stop Playback	Yes (Windows only)	K	K
Increase forward playback speed	Yes (Windows only)	L	L
Decrease forward playback speed	No	Shift+L	Shift+L
Step forward one frame	No	K+L	K+L
Step forward 1/2 second	No	Shift+K+L	Shift+K+L
Select first or next media at playhead	Yes	—	—
Select all media at playhead	Yes	—	—
Ripple Split <ul style="list-style-type: none"> • Inserts space on timeline 	No	Hold Shift and drag	Hold Shift and drag playhead

<ul style="list-style-type: none"> Moves everything to the right of the playhead 		playhead	
Ripple move	No	<ol style="list-style-type: none"> Select clip on timeline. Hold Shift and drag media. 	—
Ripple trim Extends/reduces media duration without creating space	No	Hold Shift and drag end of media in/out	—
Ripple split and move everything on track at playhead	No	Hold Shift and drag playhead	Hold Shift and drag playhead
Temporarily disable snapping	No	Hold Ctrl and drag media	Hold Ctrl and drag media
Enable timeline snapping	No	—	Command+Shift+Semicolon
Attach/detach timeline	Yes	Ctrl+3 (On Program Options tab on Windows)	Command+3

Captions

Option	Customizable	Windows Shortcut	Mac Shortcut
Add caption	Yes	Shift+C	Shift+C
Increase caption duration	Yes (Windows only)	Ctrl+Alt+]	Command+]
Decrease caption duration	Yes (Windows only)	Ctrl+Alt+[Command+[
Next caption	No	Tab	Tab
Previous caption	No	Shift+Tab	Shift+Tab
Replay current caption segment (Loop button)	No	Enter -Or- Click Loop button	Enter -Or- Click Loop button

Timeline Tray Options

Option	Customizable	Windows Shortcut	Mac Shortcut
Add marker	Yes	Shift+M	Shift+M
Add quiz	Yes	Shift+Q	Shift+Q
Show/hide marker view	Yes	Ctrl+M	Ctrl+M
Show/hide quiz view	Yes	Ctrl+Q	Ctrl+Q
Show/hide transcript view	Yes	Ctrl+T	Ctrl+T
Next marker	Yes	Ctrl+]]	Ctrl+]]
Previous marker	Yes	Ctrl+[[Ctrl+[[
Select next marker Extend selection to next marker	Yes	Ctrl+Shift+]]	Ctrl+Shift+]]
Select previous marker Extend selection to previous marker	Yes	Ctrl+Shift+[[Ctrl+Shift+[[
Next quiz (jump to and select)	Yes	Ctrl+0	Ctrl+0
Previous quiz (jump to and select)	Yes	Ctrl+9	Ctrl+9

Library Options

Option	Customizable	Windows Shortcut	Mac Shortcut
Import to library	Yes (Windows only)	Ctrl+Shift+I	—
Add selection to library	Yes	Ctrl+Shift+A	Command+Option+A
Open library tab	No	R	R
Collapse selected folder Move upwards to parent	No	Left Arrow -Or- Double-click	Left Arrow -Or- Double-click
Expand selected folder	No	Right Arrow	Right Arrow

		-Or- Double-click	-Or- Double-click
Collapse all folders	No	Ctrl+Left Arrow	Command+Left Arrow
Expand all folders	No	Ctrl+Right Arrow	Command+Right Arrow
Collapse/expand subfolders	No	Alt+Click	Option+Click
Select next element upwards	No	Up Arrow	Up Arrow
Select next element downwards	No	Down Arrow	Down Arrow
Scroll to top	No	Home	Fn+Left Arrow
Scroll to bottom	No	End	Fn+Right Arrow
Scroll to and select top	No	Ctrl+Home	Option+Command+Up Arrow
Scroll to and select bottom	No	Ctrl+End	Option+Command+Down Arrow
Scroll upwards by height of view	No	Page Up	Fn+Up Arrow
Scroll downwards by height of view	No	Page Down	Fn+Down Arrow
Delete selected items (In custom library)	No	Delete	Delete
Multi-select items	No	Shift+Click -Or- Shift+Arrow Key	Shift+Click -Or- Shift+Arrow Key
Add/remove item from selection	No	Ctrl+Click	Command+Click
Enter asset rename mode (In custom library)	No	F2	Enter

Text Options for Annotations

Option	Windows Shortcut	Mac Shortcut
Edit text	—	Option+Return
Bold	Ctrl+B	Command+Shift+B
Italic	Ctrl+I	Command+Shift+I

Select one character right of the cursor	Shift+Right Arrow	Shift+Right Arrow
Select one character left of the cursor	Shift+Left Arrow	Shift+Left Arrow
Select all characters after the cursor	Shift+Down Arrow	Shift+Down Arrow
Select all characters before the cursor	Shift+Up Arrow	Shift+Up Arrow
Underline	Ctrl+U	Command+Shift+U
Copy selected text	Ctrl+C	Command+C
Paste text	Ctrl+V	Command+V
Undo	Ctrl+Z	Command+Z
Redo	Ctrl+Y	Shift+Command+Z
Delete text	Select text and press Delete	Select text and press Delete
Align left	—	Select text and press Command+Shift+Left Bracket
Align center	—	Select text and press Command+Shift+Backslash
Align right	—	Select text and press Command+Shift+Right Bracket
Copy style	—	Command+Option+C
Paste style	—	Command+Option+V
Show special characters	—	Ctrl+Command+Spacebar


PowerPoint Add-In Shortcuts

Option	Window Shortcut
Record	Ctrl+Shift+F9
Pause	Ctrl+Shift+F9
Stop	Ctrl+Shift+F10

macOS Permissions

Learn how to enable permissions for Camtasia on macOS 10.14 or later.


Permissions are required for [TechSmith Camtasia \(https://www.techsmith.com/video-editor.html\)](https://www.techsmith.com/video-editor.html) to capture video and access the OS Photo Library. A dialog appears the first time Camtasia runs on macOS 10.14 or later.



To open the Camtasia System Permissions dialog again, click **Camtasia > Settings** (macOS 13 or later) or **Preferences** (macOS 12 or earlier) > **General tab > Camtasia System Permissions**.

Enable Permissions in Camtasia

1. In the Camtasia System Permissions dialog, click **Edit System Permissions** or the **Enable** button for a permission.
2. Complete one of the following:
 - **macOS 13 or later:** The Privacy & Security settings dialog opens. Click the corresponding Camtasia version checkbox in the right column to allow the permission.



- o **macOS 12 or earlier:** The Security & Privacy > Privacy tab dialog appears. Click the corresponding Camtasia version checkbox in the right column to allow the permission.




3. After a permission is enabled, a prompt to exit Camtasia appears. Click **Quit & Reopen** or click **Later** to manually restart Camtasia at a later time after all desired permissions are enabled.

Note: It is recommended to enable all permissions before restarting Camtasia. If you do not restart after permission changes, Camtasia may display unpredictable behavior.


Manually Edit Permissions

1. Complete one of the following:

- o **macOS 13 or later:** Open **Mac System Settings > Privacy & Security**. Click the permission type in the right column.



- o **macOS12 or earlier:** Open **Mac System Preferences > Security & Privacy > Privacy tab**. Click the permission type in the left column.



2. Click the corresponding Camtasia version checkbox in the right column to allow the permission.
3. If Camtasia is running and a permission is allowed, a prompt to exit Camtasia appears. Click **Quit & Reopen** or click **Later** to manually restart Camtasia at a later time after all desired permissions are enabled.

Note: It is recommended to enable all permissions before restarting Camtasia. If you do not restart after permission changes, Camtasia may display unpredictable behavior.

Crisp & Clear Screen Recordings

Learn how to set recording dimensions, project dimensions, and export settings to get crisp, clear video.

The following items can impact video quality:

- **Recording Dimensions:** The size of your recording. If you record full screen, the recording dimensions are usually the same as the resolution of your monitor.
- **Project Settings:** The size of your canvas in Camtasia, the editing frame rate, and audio levels.
- **Export Settings:** The options you choose when exporting your video, including the size of your video.

Adjust these settings to produce high video quality.

Recording Dimensions

One way to get a crisp, clear screen recording is to display your screen video at its original recording size, which avoids any scaling.

Scaling stretches or shrinks a screen recording to display it at a different size than the original recording. Scaling decreases quality and causes videos to appear blurry or distorted. See [Scaling Tips](#) to learn when scaling is necessary or how to use scaling to your advantage.

Tip: Start with the recording dimensions.

If you know the desired dimensions for your final video, enter these dimensions into the Width and Height fields in Camtasia Recorder for your source recording. See [Record, Edit, Share](https://www.techsmith.com/learn/?post_type=tutorial&p=182295) (https://www.techsmith.com/learn/?post_type=tutorial&p=182295).

Project Settings

Set the [canvas dimensions](#), [editing frame rate](#), and [audio levels](#) during the editing phase of your project.


Canvas Dimensions

Once you have a recording, set the canvas dimensions to the same as your recording dimensions.

Tip: Change the canvas dimensions before you begin editing your video.


Changing the dimensions after editing can skew the look of edited media.

1. Select the **Magnification dropdown** > **Project Settings**.




2. The Project Settings dialog appears.

- o To select a standard video size, click **Canvas Dimensions** (Windows) or **Dimensions** (Mac) and select a preset.



- o To enter custom width and height, click **Canvas Dimensions** and select **Custom**. Enter dimensions (in pixels) into **Width** and **Height** fields.



Note: Click the lock icon  to enable or disable the aspect ratio lock.


3. Click **Apply**.

Editing Frame Rate


Frame rates typically vary throughout a video. Record, edit, and share videos at the same frame rate to maintain video quality.

Note: To edit and export a video at a high target frame rate (60 fps), your timeline must include high frame rate video clips.

1. Right-click (Windows) or Control+click (Mac) the media in the Media Bin and select **Details** to view the actual media frame rate.



2. Select the **Magnification dropdown > Project Settings > Frame Rate dropdown** to change the editing frame rate.




3. Click **Apply**.

Consistent Audio Levels


Crisp, clear audio is also a key element of video quality. Enable the **Auto-normalize loudness** option to automatically adjust the audio loudness across clips to maintain audio consistency for a project.



1. Select the **Magnification dropdown > Project Settings** option.



2. Click to enable the **Auto-normalize loudness** option.



3. Click **Apply**.

To learn more about improving audio quality, see [Add Audio Effects \(https://www.techsmith.com/learn/?post_type=tutorial&p=196578\)](https://www.techsmith.com/learn/?post_type=tutorial&p=196578).

Export Settings

Match the dimensions or aspect ratio in recording, editing, and exporting your video to maintain video quality. Complete the following to export a video with the current project (editing) dimensions:

Windows:

1. Click the **Export** button and select **Local File**.
2. Enter a **File name** and select a **Save location**.
3. Click to display **Advanced Settings**.
4. On the **Dimensions** tab, select **Current Project Dimensions**.
5. Click **Export**.

Mac:

1. Click the **Export** button and select **Local File**.
2. Enter a file name in the **Export As** field and select a location.
3. In the **File format** dropdown, select **Export to MP4**.
4. Click the **Options** button.
5. In the **Dimensions** dropdown, select **Current** and click **OK**.
6. Click **Export**.

Scaling Tips

Sometimes You Can't Avoid Scaling

Sometimes it's not possible to match your recording and project dimensions. For example:

- If you record a screen that is bigger or smaller than the size of the video you want to create.
- Your monitor doesn't fit a standard 16:9 aspect ratio.

In these situations scaling the recording is unavoidable, but you can use scaling to your advantage.

How We Use Scaling to Our Advantage


For our tutorial videos, we record on a monitor that is twice the size of our project dimensions. The screen recording will be displayed at half its original size and will have some quality loss. This is fine for us, because we spend most of our time zoomed in and focused on specific parts of the user interface, which is where we want to see the highest quality.

To get the highest quality and most detail, we zoom to the original size of the recording, or 100% scale. To show something on an adjacent part of the screen, we pan over and remain at 100% scale.

To learn about zooming in Camtasia, see [Zoom in to Focus Attention \(https://www.techsmith.com/learn/?post_type=tutorial&p=182337\)](https://www.techsmith.com/learn/?post_type=tutorial&p=182337).

Follow the 100% Rule

When in doubt, keep your screen recording at 100% scale. This displays it at the highest quality possible.




Find Camtasia Assets on the Website

Learn how to download assets for your videos from the TechSmith Assets for Camtasia website or in Camtasia version 2023.2.0 and earlier.

Camtasia Assets Overview

In Camtasia 2023.3.0 and later, our free and premium assets are now easier than ever to access and add to your projects. You can browse over 100 million professional, royalty-free video assets directly in Camtasia. Add polish to your video with photos, videos, audio, and customizable digital content, without ever leaving the Camtasia Editor. See [Enhance Your Video with Camtasia Assets](https://www.techsmith.com/learn/tutorials/camtasia/camtasia-assets/) (<https://www.techsmith.com/learn/tutorials/camtasia/camtasia-assets/>).



This tutorial covers how to download assets directly to your computer from the [TechSmith Assets for Camtasia](https://library.techsmith.com/en/Camtasia) (<https://library.techsmith.com/en/Camtasia>) website or in Camtasia version 2023.2.0 or earlier.

Camtasia Asset Types

The following types of assets are available to download from [TechSmith Assets for Camtasia](https://library.techsmith.com/en/Camtasia) (<https://library.techsmith.com/en/Camtasia>) or from the **Camtasia Assets** subtab in Camtasia version 2023.3.0 or later.

▼ Customizable

- Titles

Capture the attention of your viewers with the perfect title animation. Easily add your logo, text, and colors to make it your own.

- **Dynamic Backgrounds**

Looping background animations for your next project. Customize speed, color, skew, and more. See [Add a Dynamic Background \(https://www.techsmith.com/learn/tutorials/camtasia/dynamic-backgrounds/\)](https://www.techsmith.com/learn/tutorials/camtasia/dynamic-backgrounds/).

- **Motion Graphics**

Get your point across with ease. Choose from hundreds of motion graphics, like lower thirds, [callouts \(https://www.techsmith.com/learn/tutorials/camtasia/annotations/\)](https://www.techsmith.com/learn/tutorials/camtasia/annotations/), animations, and more to create powerful explainer and product videos.

- **Callouts**

Annotations, animations, and customizable graphics designed to focus viewer attention: arrows, indicators, shapes, and more. See [Add Arrows, Shapes, and Callouts \(https://www.techsmith.com/learn/tutorials/camtasia/annotations/\)](https://www.techsmith.com/learn/tutorials/camtasia/annotations/).

- **Templates**

Create video faster than ever with drag and drop video templates you can customize in just a few clicks. See [How to Use a Template \(https://www.techsmith.com/learn/tutorials/camtasia/use-a-template/\)](https://www.techsmith.com/learn/tutorials/camtasia/use-a-template/).

- **Asset Packs**

Themed video elements thoughtfully curated to help you accomplish your goals.

- **Themes**

Customizable themes instantly make your video look more professional and polished with coordinated colors and fonts. No graphic design experience necessary! See [Build Your Color Palette \(Themes\) \(https://www.techsmith.com/learn/tutorials/camtasia/themes/\)](https://www.techsmith.com/learn/tutorials/camtasia/themes/).

- **Device Frames**

Quickly make any video look like it's playing on a desktop, laptop, or mobile device screen. Establish context and add a level of professionalism to your videos with customizable device frames. See [Provide Context with Device Frames \(https://www.techsmith.com/learn/tutorials/camtasia/device-frames/\)](https://www.techsmith.com/learn/tutorials/camtasia/device-frames/).

▼ Videos

- **Footage**

Enhance your video projects with royalty-free footage. Explore millions of high-quality video clips that bring your stories to life.

- **Animations**

These fun and expressive animations help you convey emotion, simplify complex ideas, and will delight your viewers.

- **Motion Backgrounds**

Make your videos pop with animated, looping video backgrounds. Explore millions of royalty-free motion backgrounds.

- **Effects**

Find the perfect video effect to improve your next video. Video effects library of royalty-free, short clips with an alpha channel.

▼ Images

- **Photos**

Bring your ideas to life with stunning, royalty-free photos.

- **Icons**

Discover the perfect royalty-free illustrations and icons for your next video project.

▼ Audio

- **Music**

Find high-quality background music for videos. Explore royalty-free instrumental and vocal audio tracks in various moods, styles, and genres.


- **Sound Effects**

Emphasize important content in your video with sound effects. Find the perfect royalty-free sound effect to accompany the action on screen.


Download Assets in Camtasia (Version 2023.2.0 and Earlier)

In Camtasia version 2023.2.0 and earlier, complete the following to import downloaded assets into your Downloads library for quick use in a video project:

1. In TechSmith Camtasia, click the **Downloads button** > **Download more assets**.




2. The [TechSmith Assets for Camtasia website \(https://library.techsmith.com/camtasia\)](https://library.techsmith.com/camtasia) opens. Sign in with your TechSmith account.
3. Hover your cursor over an asset to preview it.
4. Click the **Send to Camtasia** button to download the asset into Camtasia.



Note: You must have Camtasia version 2019 or later to open assets directly in Camtasia. For previous versions, see [Download Assets to Your Computer](#).

In Camtasia, the asset downloads to **Library tab > Library dropdown > Downloads** and appears in the list of downloaded assets under the **Downloads** button.




Note: To access device frames in Camtasia, select **Visual Effects** tab and drag the **Device Frame** effect onto media on the timeline. Click the **Properties** button and select the desired device frame from the **Type** dropdown. See [Provide Context with Device Frames \(https://www.techsmith.com/learn/tutorials/camtasia/device-frames/\)](https://www.techsmith.com/learn/tutorials/camtasia/device-frames/).

Download Assets to Your Computer


To learn how to download assets onto your computer from the [TechSmith Assets for Camtasia \(https://library.techsmith.com/en/Camtasia\)](https://library.techsmith.com/en/Camtasia) website, complete with the following based on your web browser:

▼ Google Chrome

1. Go to the [TechSmith Assets website \(https://library.techsmith.com/camtasia\)](https://library.techsmith.com/camtasia) and sign in with your TechSmith Account.
2. Hover your cursor over an asset to preview it. Click the **Download** button.




3. Google Chrome downloads the asset into your Downloads folder. Click the **Downloads** button in the upper-right corner of your web browser and click **Show in folder**.




To add the asset to Camtasia, see [Add Assets to Camtasia](#).

▼ Microsoft Edge


1. Go to the [TechSmith Assets website \(https://library.techsmith.com/camtasia\)](https://library.techsmith.com/camtasia) and sign in with your TechSmith Account.
2. Hover your cursor over an asset to preview it. Click the **Download** button



3. At the bottom of your web browser, click the **Save** button.




4. Microsoft Edge downloads the asset into your Downloads folder. At the bottom of your web browser, click the **Open folder** button.




To add the asset to Camtasia, see [Add Assets to Camtasia](#).

▼ Firefox


1. Go to the [TechSmith Assets website \(https://library.techsmith.com/camtasia\)](https://library.techsmith.com/camtasia) and sign in with your TechSmith Account.
2. Hover your cursor over an asset to preview it. Click the **Download** button



3. A dialog appears. Select **Save File** and click **OK**.




4. Firefox downloads the asset into your Downloads folder. Click the **Downloads** button in the upper-right corner of your web browser.




To add the asset to Camtasia, see [Add Assets to Camtasia](#).

▼ Internet Explorer


1. Go to the [TechSmith Assets website \(https://library.techsmith.com/camtasia\)](https://library.techsmith.com/camtasia) and sign in with your TechSmith Account.
2. Hover your cursor over an asset to preview it. Click the **Download** button




3. At the bottom of your web browser, click the **Save** button.



4. Internet Explorer downloads the asset into your Downloads folder. At the bottom of your web browser, click the **Open folder** button. To add the asset to Camtasia, see [Add Assets to Camtasia](#).




5. A security dialog appears. Click the **Allow** button.



▼ Safari

1. Go to the [TechSmith Assets website \(https://library.techsmith.com/camtasia\)](https://library.techsmith.com/camtasia) and sign in with your TechSmith Account.
2. Hover your cursor over an asset to preview it. Click the **Download** button



3. Safari downloads the asset into your Downloads folder.

To add the asset to Camtasia, see [Add Assets to Camtasia](#).

Add Assets into Camtasia (Version 2023.2.0 and Earlier)

If you downloaded an asset to your computer, complete the following to add the asset to Camtasia:

Asset File Format	How to Add to Camtasia
LIBZIP (Titles, Motion Graphics, Audio Visualizers)	<ol style="list-style-type: none"> 1. Double-click the .libzip file. 2. Camtasia opens. In the Import to Library dialog, select Create New Library or select an existing Library to add the asset to. 3. Click the Import button.
CAMPACKAGE (Templates, Asset Packs, Themes)	<p>Double-click the .campackage file.</p> <p>A dialog appears and lists the imported resources. See Package and Share Camtasia Resources (https://www.techsmith.com/learn/?post_type=tutorial&p=182342).</p> <ul style="list-style-type: none"> • To access templates, select File > New Project from Template. The template is located in the Template Manager. • To access asset packs, click Library tab > Library dropdown. The asset packs are located in the User Library section. • To access themes, select File (Windows) or Camtasia (Mac) > Manage Themes or select a theme in the Theme dropdown in the Properties panel.
TSCDF (Device Frames)	<p>Double-click the .tscdf file.</p> <p>The device frames are added to the Type dropdown in the properties. Add a Device Frame effect to the timeline to access the device frame properties. See Provide Context with Device Frames (https://www.techsmith.com/blog/?post_type=tutorial&p=182330).</p>

MP4

(Footage,
Motion
Backgrounds)





MP3

(Music, Sound
Effects)

JPG

(Photos,
Illustrations,
Icons)

1. In Camtasia, select **File > Library > Import Media to Library** or drag and drop the asset into the Library.
2. Select the asset and click **Open** on Windows and **Import** on Mac.
3. In the Add to Library dialog, select a Library from the dropdown.
4. Click **OK**.

MODE	NONE	ALPHA	ALPHA INVERT	LUMINOSITY	LUMINOSITY INVERT
PREVIEW WINDOW					
TIMELINE					

DETAILS

NONE

Both objects appear. The shape on track 2 covers the text on track 1

ALPHA

Tracks reveal what is directly under it. If the green object is above ABC, then ABC will be visible when ALPHA is applied

ALPHA INVERT

Conceals what is directly under it. If the green object is above ABC, then ABC will NOT be visible. But DEF will be.

LUMINOSITY

Mattes reveal what is white or bright in the track below it. In this case, the white is on top of AB and therefore it comes through as normal. Gray is only 50% "bright" or luminous, so the letters CD are 50% transparent.

LUMINOSITY INVERT

Conceals what is white or bright in the track below it. In this case, the white part of the graphic hides the AB. EF are visible because Luminosity invert shows things that sit beneath a black object.

SHORTCUTS



Next Clip

Ctrl Alt Period

Ctrl Period

Previous Clip

Ctrl Alt Comma

Ctrl Comma

Step Forward

Period

Period

Step Backward

Comma

Comma

Play / Pause

Space Bar

Space Bar

Split Selected Media

S

Cmd T

Add Placeholder

P

P

Select All

Ctrl A

Cmd A

*Many shortcuts can be reassigned (Preferences > Shortcuts)



Recording



Pause / Resume

F9

Cmd

Shift

2

Stop

F10

Cmd

Option

2

Add Marker

Shift

M

Editing

Annotations

N

N

Split

S

Cmd

T

Custom Animation

Shift

A

Shift

A

Add Last Transition

Shift

T

Shift

T

Group

Ctrl

G

Cmd

G

Ungroup

Ctrl

U

Cmd

U

Split All

Ctrl

Shift

S

Cmd

Shift

T

Stitch

Ctrl

Alt

I

Cmd

Option

I

Play / Pause

Space Bar

Space Bar

Step Forward

Period

Period

Step Backward

Comma

Comma

Add Marker

Shift

M

Shift

M

Next Marker

Ctrl

]

Ctrl

]

Previous Marker

Ctrl

[

Ctrl

[

Zoom

Ctrl

+/-

Cmd

+/-

Alt / Option

1. Hold **Alt/Option**, then click and drag the handle of an object on the canvas to crop the object.
2. Hold **Alt/Option**, mouse over the edge of a clip on the timeline, then click and drag to extend the frame of that clip.

Shift

1. Hold **Shift** while moving media to move all other media on the same track
2. Hold **Shift** while moving the playhead to split and move all media at once